Poultry Water Quality Handbook

Printed with the Permission of
The Water Quality Consortium

Peterson Farms
P.O. Box 248 • Decatur, Arkansas, USA 72722
Decatur Sales Office Telephone: 501-752-5000 • Fax: 501-752-5678
Email: PetersnHR@aol.com • Peterson Farms Web Site Address: www.petersonfarms.com

PIGEON.0612

4:05-cv-00329
State's Exhibit 0364

Exhibit 52

Peterson Farms, Inc. P.O. BOX 248 DECATUR, ARKANSAS 72722 PHONE: (501) 752-5000 FAX: (501) 752-5650

Dear Peterson Grower

The protection of our environment and in particular of our region's water quality is of great importance to Peterson Farms. We, as a company, are committed to doing everything we can to insure generations to come have a clean water supply. You, our growers, have made clear your commitment to our environment.

Peterson Farms feels it is important to provide you with the most up-to-date information on water quality; information that will serve as a tool in managing your poultry operation. This book was written by the Poultry Water Quality Consortium for our industry. Using the information in this book will show your commitment and willingness to be stewards of our environment!

Please take the time to review the information in this book. Use it as a resource for making the right choices and following the right management practices in your operation. Peterson Farms will continue to provide you with the most up-to-date information available. Thank you for your time and commitment to this important issue.

Sincerely

Dan Henderson

Dan Henderson
President of Peterson Farms

Preface to the Second Edition

Air, land, and water — the environment — is more than the place where we live; it is the cornerstone of our quality of life. Every industry, every company, every individual has a stake in the environment.

The poultry industry recognizes the significance of its stake in the environment and the importance of conservation. Protecting the environment from the unintended consequences of production has always been a concern; the phenomenal growth and progress of the industry in recent years have made it a priority. The challenges that come with rapid advancement (e.g., new ways of livestock farming, changing patterns of rural development, water and soil quality) are often too complex to be solved easily or quickly. The challenges are environmental, economic, and social; and they demand cooperation, a free exchange of information, and access to technologies that can help us manage and use poultry by-products as resources, not as wastes requiring disposal.

In pursuit of this goal, the industry and several government agencies created a new venture: the Poultry Water Quality Consortium, to protect natural resources by promoting environmental management. An interagency/industry agreement signed in 1991 and renewed in 1996 formally established the consortium, which includes the following members:

- U.S. Poultry and Egg Association,
- Tennessee Valley Authority,
- U.S. Environmental Protection Agency, and the
- USDA Natural Resources Conservation Service.

The Poultry Water Quality Consortium is a cooperative effort to identify and adopt environmentally prudent uses of poultry by-products. The first edition of the **Poultry Water Quality Handbook** (1994) helped prove the value of teamwork and the successful outcomes that can be expected from the combined efforts of people and organizations, industry and government. No one is excluded from responsibility, not farmers, service providers, company management, or government officials.

The second edition of the handbook reflects the progress made in environmental management since the early 1990s, especially in the development of markets for manure and litter; the diffusion of composting methods; and the emergence of new technologies for mortality, air quality and nutrient management. Growers should find practical help in these pages — but perhaps also a glimpse of how large the community is that shares their goal. Indeed, with so many research projects and field trials now underway, supported by so many people on farms and in university, government, and industry organizations, the industry is in an excellent position to continue its role as an environmental leader.

The Poultry Water Quality Handbook seeks to consolidate information, ideas, and references to enhance water quality. As the adventure continues, the handbook, which the Consortium will continue to format as fact sheets (to encourage their wide distribution, use, and reuse) — will be revised and updated to include new technology and techniques that will ensure the quality of water for everyone.

U.S. Poultry & Egg Association

ACKNOWLEDGMENTS

The *Poultry Water Quality Handbook* was prepared under the direction of the Poultry Water Quality Consortium members, with Richard D. Urban as Managing Editor, and the invaluable assistance of Richard C. Strickland, Tennessee Valley Authority, Muscle Shoals, Alabama; Barry Kintzer, USDA Natural Resources Conservation Service, Washington, D.C.; Ira H. Linville, U.S. Environmental Protection Agency, Atlanta, Georgia; Richard D. Reynnells, Cooperative State Research, Extension, and Education Service, Washington, D.C.; and Lewis E. Carr, University of Maryland, College Park. References to source material are shown on the information sheets in the handbook.

Other major contributors who have given their time and knowledge to help organize and write this handbook are the following:

- **John P. Blake**, Auburn University, Poultry Science Department, Auburn, AL 36849-5416
- **Julian D. Brake**, Nutritionist Prestage Farms, 4651 Taylors Bridge Road, Clinton, NC 28329
- **Don Dalton**, U.S. Poultry & Egg Association, 1530 Cooledge Rd., Tucker, GA 30084-7303
- **James Donald**, Auburn University, 228 Ag Engineering Building, Auburn, AL 36849-5626
- **Jesse L. Grimes**, North Carolina State University, 208 Scott Hall, Box 7608, Raleigh, NC 27695-7608
- **Judith Grizzle**, Department of Animal Science, University of Tennessee, Knoxville, TN 37760-1071
- **Joseph Hess**, Auburn University, 251 Animal Science, Auburn, AL 36849-5416
- **Patricia Y. Hester**, Department of Animal Sciences and Forestry Natural Resources, Purdue University, West Lafayette, IN 47907
- **Jess Lyons**, Department of Animal Science, University of Missouri, Columbia, MO 65211
- **Joann Manhart**, Missouri Poultry Federation, 225 East Capitol, Jefferson City, MO 65101
- **Tom McCaskey**, Auburn University, Department of Animal and Dairy Sciences, Auburn, AL 36849-5415
- **Philip Moore**, Plant Sciences 115, University of Arkansas, Fayetteville, AR 72701
- **Paul L. Ruszler**, Extension Poultry Scientist, Virginia Tech, Animal and Poultry Science Department, Blacksburg, VA 24061-0306
- **Nabil W. Said**, Triple "F", Inc., 10104 Douglas Avenue, Des Moines, IA 50322
- **J.M. Vandepopulier**, University of Missouri, S105 Animal Science Center, Columbia, MO 65211
- **Karl VanDevender**, Cooperative Extension Service, P.O. Box 391, Little Rock, AR 72203
- **Ralph Williams**, Department of Entomology, Purdue University, Lafayette, IN 47907

Recognition is given to Rachel Reeder, JT&A., inc., Washington, D.C., for her invaluable assistance in writing and editing this handbook and to Lura Svestka, JT&A, inc., for the design and typesetting.

Special recognition is given to Johnnie Elizabeth Sanders for all her time and efforts in helping with the coordination activities, reviewer contacts, and all the details that had to be accomplished for this Handbook to become a reality.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWQH / 0 — 9/98

POULTRY WATER QUALITY CONSORTIUM

6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411

Tel: 423 855-6470 • Fax: 423 855-6607

CONTENTS

PREFACE

Preface to the Second Edition
Acknowledgments

WATER QUALITY ISSUES (WQI)

Introducing the Poultry Industry — Its Environmental Issues and Impacts	WQI / 1
Protecting the Environment and Water Quality	WQI / 2
What Is Water Quality?	WQI / 3
Poultry Production and Water Quality	WQI / 4
Understanding Water Quality Regulations	WQI / 5
Drinking Water Quality — Protecting Your Birds' Health and Performance	WQI / 6

POULTRY WASTE MANAGEMENT (PWM)

Environmental Impacts of Poultry Waste	PWM / 1
Planning Poultry Waste Management	PWM / 2
Dry Waste Management	PWM / 3
Liquid Waste Management	PWM / 4
Composting Waste Products	PWM / 5
Putting Nutrient Management to Work	PWM / 6
Economics of Transporting Poultry Wastes	PWM / 7
Feeding Litter to Beef Cattle	PWM / 8
Horticultural Uses of Litter	PWM / 9
Controlling the Effects of Ammonia and Phosphorus	PWM / 10

POULTRY MORTALITY MANAGEMENT (PMM)

An Overview of Poultry Mortality Management	PMM / 1
Burial — A Disposal Method for Dead Birds	PMM / 2
Incineration — A Disposal Method for Dead Birds	PMM / 3
Composting — A Disposal Method for Dead Birds	PMM / 4
Mortality Composters — Small Bins, Minicomposters and Packaged Deals	PMM / 5
New Takes on the Rendering Process — Refrigeration, Fermentation, and Acid Preservation	PMM / 6
Developing Alternative Markets for Poultry Mortalities	PMM / 7
Humane Methods for Dealing with Spent Hens	PMM / 8

CONTENTS

OTHER ENVIRONMENTAL ISSUES (OEI)

Site Selection for the Poultry Farmstead	OEI / 1
Using Regulations as Management Principles	OEI / 2
Air Quality and Its Management	OEI / 3
Controlling Odor — Multiple Purpose Management	OEI / 4
Preventing Fires in Manure/Litter Storage Structures	OEI / 5
Controlling Struvite Buildups	OEI / 6
Protection Against Pests, Predators, and Darkling Beetles	OEI / 7
Protection Against Pests — Controlling Flies	OEI / 8

RESOURCE INFORMATION (RI)

Poultry Water Quality Consortium	RI / 1
U.S. Poultry & Egg Association	RI / 2
USDA Natural Resources Conservation Service	RI / 3
Tennessee Valley Authority	RI / 4
U.S. Environmental Protection Agency	RI / 5
Directory of Poultry Associations	RI / 6
Other Agencies Supporting the Poultry Industry	RI / 7
USDA Farm Service Agency	
USDA State Cooperative Research, Education, and Extension Service	
Directory of State Water Quality Agencies	RI / 8

Introducing the Poultry Industry — Its Environmental Issues and Impacts

In the United States, poultry is a major source of agricultural income. In 1996, according to the National Agricultural Statistics Board, the combined value of production from broilers, eggs, turkeys, and sales of chickens contributed $21.8 billion to the economy — an 18 percent increase over the $18.5 billion reported in 1995.

U.S. Leadership and International Influence

In 1996, the United States exported 2.3 million metric tons of poultry meat — nearly four times as much as any other nation and twice as much as Brazil and Hong Kong combined, the next largest exporters of poultry meat products. The United States also leads the world in total egg exports. In 1996, the United States exported nearly five times as many eggs as China, the next largest egg exporter, while China exported nearly twice as many eggs as the next largest egg exporters, Denmark, Germany, the Netherlands, and Turkey.

During the same period, inhabitants of the United States consumed 12.1 million metric tons of poultry meat. China, at 11.3 million metric tons, was the second largest consumer of poultry meat. The per capita consumption of poultry meat in the United States reached nearly 45.6 kilograms or 100.76 pounds per annum in the United States in 1996, with demand in Israel nearly keeping constant, and Hong Kong's consumption increasing slightly. Preliminary figures for 1997 show the United States consumed slightly more poultry meat (per capita) than any other nation, as traditionally recorded.

Thus, the United States produces more poultry, consumes more poultry, and exports more poultry than any other nation in the world.

Simultaneously, however, growing populations and rising per capita incomes are leading to increased poultry production in other nations. In fact, the number of chickens reported on a worldwide basis increased 53 percent between 1980 and 1990 — the increase in Asia alone was over 100 percent. Indeed, the technological expertise that underlies the U.S. poultry industry's phenomenal growth can be easily communicated or "transferred" to developing nations, where poultry is important to support growing, more affluent populations. The industry's growth in these nations can also be expected to continue.

Fueling the Growth

Both genetics and efficiency contribute to the magnitude and value of the U.S. poultry industry. In 1996, for example, broiler production was up 4 percent; egg production, up 2 percent; and the value of turkeys and other chickens also increased. In round numbers, the National Agricultural Statistic Service indicates that U.S. growers raised more than 7.6 billion broilers in 1996; handled 76.1 billion eggs; and marketed 7.17 billion pounds (live weight) of turkey. The number of other chickens (excluding broilers) sold in the United States during 1996 totaled 174 million, a 3-percent decrease from the total sold during 1995 (however, the value of trade in this category increased fractionally despite this decline).

The number of people employed in the industry is difficult to compute, especially if one includes very small operations, and the many off-farm laborers who work in hatcheries, live-bird processing plants, feed mills, and other allied operations serving the industry. Nevertheless, about 70,100 farms reported poultry inventories to the 1992 Census of Agriculture (so that type of farm = poultry); and during the same Census, some 35,000 operations reported poultry-related sales of $1,000 or more under the Standard Industrial Classification (SIC) 025 for poultry and eggs. That is,

- 18,284 farms are categorized as "broilers, fryers and roaster chickens" (SIC 0251);
- 10,636, as "chicken eggs" (SIC 0252);
- 3,361, as "turkey and turkey eggs" (SIC 0253);
- 427, as "poultry hatcheries" (SIC 0254); and
- 2,358, as "poultry and eggs, n.e.c." (SIC 0259).

These numbers establish only the minimum threshold for the size of the industry; however, the estimated and combined value of these markets to each state (based on cash receipts collected in 1996) are shown in Figure 1. The income figures are impressive — as they have been for almost 30 years — and they are expected to increase — probably as much as 5 percent each year into the future.

Responsible Waste Management — the Environmental Challenge

Such impressive growth is accompanied by an additional yearly legacy. Every increase in poultry production increases the production of manure, used litter, carcasses, and the flow of wastewater from hatchery, egg, layer, and live-bird processing operations. These by-products must be safely disposed of, or used, to ensure that they do not lead to air or water pollution. The challenge for the industry is where and how to use these poultry wastes to benefit the grower and protect the environment.

The rapid growth of the poultry industry internationally only augments the challenge, as does the clustering of poultry operations near food processing plants or large urban markets. The problem is simple to explain, but not so easily solved.

The traditional use for poultry by-products is land application, but land resources are not always sufficient. Expanded or new uses for poultry waste must be sought: for example, poultry waste can and has been used as an ingredient in organic fertilizers, as a horticultural and mushroom growing medium, and as an ingredient in feed products for livestock, dogs, cats, and aquaculture. Indeed, a continuing search for additional uses is part of the challenge of modern production methods.

The poultry industry is committed to protecting water and air quality, the environment and natural resources. Growers in particular share responsibility with other segments of the agricultural community and all citizens for nonpoint source pollution: the pollution that originates from diffuse sources (e.g., agricultural runoff, urban stormwater runoff, and erosion). Some segments of the poultry industry may also contribute to point source pollution: the pollution that issues from a known or direct discharge (e.g., wastewater discharged from the end of a pipe or discharges from processing or treatment plants).

Understanding the complexity of poultry operations can help us address these potential water quality and environmental issues. The industry is separated into hatchery, breeder, broiler-roaster-Cornish game hens (meat types), and turkey, egg, duck, and other poultry and live-bird processing operations. Each of these operations produces dry or liquid waste and dead birds. Recent developments have shifted environmental awareness beyond live-bird processing plants (offal, feathers, and wastewater) to focus on growers. The shift reflects an increasing awareness of how agricultural runoff affects water quality. It also recognizes that the growth of the industry (and its concentration in certain regions) elevates animal waste management to the status of a major problem.

An Outcome of Modern Production Methods

As any poultry grower knows, the speed, efficiency, and methods used to produce poultry and poultry products have changed drastically during the last 25 years as growers applied

mass production techniques to farming operations and brought the benefits of information technology to the farm. As a result, most poultry are grown in confined operations with limited use of water, except for drinking water for the birds. These conditions and changes require each producer to dispose of or use immense quantities of waste.

Any waste, improperly handled, can pollute the environment. In this respect, poultry operations are no different from other human activities, and though each operation is unique, most if not all of the problems can be prevented or solved through proper waste disposal or utilization methods and changes in management style or production techniques. The solutions are not going to be uniform because each operation is different. Still, each one will begin with a model, a technology, or a case history that others can apply and adapt to their own situations.

It is important for growers to know at the beginning of the production cycle (1) how much waste will result from their operations; (2) how they can measure its chemical and physical make up; and (3) how they can account for its potential impacts on water quality, the environment, and human health. In addition, growers must know (4) how and when such impacts will occur, and (5) what measures they can take to prevent these impacts and manage the waste in an environmentally safe manner.

The overriding environmental issue facing growers today is to prevent poultry waste from adversely affecting water and air quality. Potential water pollutants from on-farm poultry operations can be classified as (1) nutrients and salts, (2) organic materials, (3) bacteria, and (4) viruses. Potential air pollutants are dust and volatile organic compounds [gases], and odor, which is primarily a nuisance.



Figure 1.—Poultry cash receipts for 1996 (in dollars).

These on-farm pollutants may originate in manure, litter, or dead birds. How such wastes are disposed of, treated, or managed will directly influence the cleanliness and safety of surface and groundwater resources. Air quality may also be affected by improperly handled poultry by-products. Air and soil are less obvious but no less important media for transporting these pollutants into the environment.

Disposing of spent hens (breeders or table egg layers after their production cycle) and dead birds is an increasing problem. The daily numbers and volume of dead birds will be predicated on the birds' age and weight, the number of birds in the poultry house, and climatic conditions. Acceptable methods of disposal include (1) burial, (2) incineration, (3) composting, and (4) rendering. Burial pits may have severe environmental limitations in areas of porous or fractured soils that would allow leaching of nutrients to groundwater. Incineration has some limitations, including the possibility of air pollution and increased fuel and labor costs.

Many progressive growers are switching to composting or to rendering as preferred solutions from an environmental and economic viewpoint. A grower must choose a method compatible with his or her individual operation and company preference. Dead birds must be treated as a resource that can add value to a grower's operation. Improper methods of disposal are unacceptable and cannot be condoned.

The magnitude of the problem underscores the advantage to be gained from its alternative: namely, that properly managed poultry wastes from manure, litter, dead birds, and wastewater are profitable farm investments. An effective waste management plan provides for the proper collection, storage, handling, and use of poultry waste. Products derived from wastes will reduce chemical fertilizer costs, improve soil quality, and protect water resources, air quality, and human and animal health. Effective waste management will also promote a favorable public attitude toward the industry.

There is not a single best or optimal approach to protect or preserve water quality and the environment. Good waste management practices are essential if the poultry industry is to continue to grow and thrive under today's environmental and societal challenges. The remainder of this handbook relates to poultry waste management (PWM) and poultry mortality management (PMM), and wastewater concerns. Information sheets on these topics provide management "guidance" to help poultry producers make sound environmental decisions; additional fact sheets discuss other environmental issues (OEI) and alternative technologies (AT). Sources of assistance are profiled in the section on Resource Information (RI).

In general, environmental needs and solutions are site specific and regional in nature. Local sources of information, including industry associations, appropriate state agencies, soil and water conservation districts, and the USDA Natural Resources Conservation Service and Cooperative Research Extension, and Education Service offices, should be consulted to ensure that your waste management plan complies with all state and federal regulations.

Producers using this handbook are encouraged to seek assistance from local, state and federal agencies, private consultants, and other professionals on how to implement waste management techniques that protect water quality and the environment. Water quality regulations and permitting requirements vary from state to state and may be more stringent than national regulations.

References

Agricultural Statistics Board. 1997. Poultry Production and Value: 1996 Summary. Pou 3-1. USDA National Agricultural Statistics Service, Washington, DC.

———. 1997. Production, Price and Value for Broilers, and Chickens Lost or Sold, 1990-1996. USDA National Agricultural Statistics, Livestock and Economics Branch, Washington, DC.

Narrod C., and C. Pray. 1993. Technology Transfer in the Poultry Industry: Factors and Externalities Associated with Increased Production. Pages 523-532 *in* Kenneth Steele, ed., Animal Waste and the Land-Water Interface. CRS Lewis, Publishers, Boca Raton, FL.

U.S. Department of Commerce. 1992. 1992 Census of Agriculture: Geographic Area Series, the United States Summary and State Data. AC92-A-51. Economics and Statistics Administration, Bureau of the Census, U.S. Government Printing Office, Washington, DC.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

WQI / 1 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Protecting the Environment and Water Quality

Protecting natural resources is a major goal of the agricultural community in general, and poultry producers in particular, who care about the environment. The quality of our air, soil, and water resources, the welfare of our animals, and human health issues are important to us and to our children; they are our connection to the future. Water quality is the most important environmental concern of the poultry industry.

Environmental protection begins with awareness. We have to know what's at stake when we read or hear about water quality and conservation, or that high concentrations of nitrates or other contaminants have been found in surface and groundwater. We need to understand how the industry's waste management affects water quality. Above all, we must be able to assess the opportunities we have, as private producers and as an industry, to meet these environmental challenges head on.

Poultry growers and the industry must be concerned about the quality of water that comes into and flows from their farms or plants. The industry's first concerns are those that everyone shares: Does the water we use support our needs? Is it drinkable (potable) and palatable? What does it cost to supply water to our homes and businesses? Would additional costs for water treatment ensure its safety for our use?

Where the Water Is

Water covers 70 percent of the earth's surface, but only 3 percent of the earth's water is usable by plants, animals, and humans. Usable water exists either as surface water or groundwater. Surface water is the runoff that flows above ground through rivers, streams, and springs until it eventually drains into the sea or oceans. The land area that collects runoff in defined locations is called a watershed, and no matter how far one lives from the water, everyone lives in a watershed (see Fig. 1).

Groundwater is water that percolates through the soil or enters the earth's subsurface through sinkholes, permeable soils, and fractures in rock formations. The underground water formation is known as an aquifer within which the groundwater moves in various directions. Some aquifers are several hundred feet deep while others lie near the surface of the earth. The upper level of shallow aquifers is called the water table. It rises and falls depending on how dry or wet the season is, or how much groundwater is extracted for use.

Water is a renewable resource; therefore, surface and groundwater are constantly being replenished. But water can also be used up faster than it can be renewed or, in the case of groundwater, "recharged." Groundwater recharge is enhanced by limiting runoff. Human activities that speed runoff or add contaminants to surface and groundwater must be controlled. Land sediments, animal wastes, sewage, pesticides, detergents, oils, and grease are some of the human contributions to poor water quality.

Understanding Water Pollution

Strictly speaking, pure water does not exist. Even rainfall contains gases, dust, and ions acquired from the air. In fact, water (a molecule containing two hydrogen atoms and one oxygen atom) is a solvent; its ability to dissolve substances is essential to plant and animal life. Most of the substances, elements, or com-



Figure 1.—Water-resources regions of the United States.

pounds that we think of as pollutants are also found naturally in water: nitrogen, phosphorus, potassium, calcium, magnesium, sodium, bicarbonate, chloride, sulfate, carbon dioxide, oxygen, and some heavy metals. But when one or more of these substances is found in excessive amounts, the water's use is impaired and the water may be considered polluted.

Potentially polluting substances, sometimes called dissolved substances or solids, can be organic or inorganic, and they occur in natural interaction among the elements of earth and sky. Their effects include color (or lack of clarity), an offensive taste, and odor. They can be added to the water during industrial, agricultural, silvicultural, land development, or other activities that serve human needs and pleasures. In the poultry industry, for example, components of manure, dead birds, and wastewater include nutrients that may be released to water through direct discharge, excessive runoff from the land, or leaching through the soil.

We expect, then, to find some dissolved substances in water; however, water's properties are degraded — its quality impaired — if it contains chemical, biological, physical, or radiological substances in sufficient quantity to restrict its use. Water quality standards defined by the U.S. Environmental Protection Agency (EPA) identify what substances must not appear in water and at what concentrations other substances may be permissible under certain conditions. Tests or analyses that must be performed on drinking water, surface, and groundwater to assess water quality illustrate the complexity of the issue.

This information sheet introduces the topic of water quality. Poultry growers and others should always check with local health agencies or state departments of environmental protection or similar agencies to ensure that they have access to current water quality criteria and standards applicable to their location. Water quality criteria are published in the Federal Register as they are developed.

References

Kintzer, B.E. 1990. How poultry waste management can prevent contamination of ground and surface water. Pages 15-21 *in* Proceedings of the 1990 National Poultry Waste Management Symposium. National Poultry Waste Management Symposium Committee, Auburn University Printing Service, Auburn, AL.

National Pork Producers Council. 1992. Guide to Environmental Quality in Pork Production. National Pork Producers Council, Environmental Task Force, Des Moines, IA.

Truitt, G.B. Jr. 1990. Why address the problem? An overview of the poultry system's response to major environmental issues. Pages 7-14 *in* Proceedings of the 1990 National Poultry Waste Management Symposium. National Poultry Waste Management Symposium Committee, Auburn University Printing Service, Auburn, AL.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

WQI / 2 — 12/97

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

What Is Water Quality?

Public domestic water supplies are regularly tested or analyzed for pollutants or contaminants. The results can be obtained from local health departments or appropriate state agencies. Private water supplies or wells should also be analyzed.

The most common tests for water quality analyze (1) pH (the level of hydrogen ions in the water), (2) total alkalinity, (3) total hardness, (4) salts, (5) chlorine, (6) dissolved oxygen, (7) metals, and (8) pathogens. Sometimes water needs to be tested for heavy metals, such as copper, lead, mercury, or zinc; or for toxins, such as DDT or atrazine. In some areas of the country, tests for radiological contaminants may be needed.

Chemical Properties

The following parameters are of importance to the poultry industry.

- The measure of pH in water determines its acidic or alkaline quality on a relative scale. (For example, in a solution of hydrochloric acid, the pH may be 3; for sodium hydroxide, it may be 12.) In water, on a scale from 0 to 14, a pH measure of 7 is neutral; for drinking water for humans and animals, the desirable measure of pH is 6.5 to 8.

- The total alkalinity of water is a measure of its capacity to neutralize acidity, which is usually expressed in milligrams per liter of calcium carbonate (mg/L of $CaCO_3$). Natural waters may have less than 50 or as many as 500 mg/L of $CaCO_3$. These variations may be affected by the rocks and soils that the water passes through. The alkalinity varies with pH and hardness, but sudden fluctuations may indicate a contaminant.

- Water also contains total dissolved solids (TDS) and minerals. TDS represent the soluble mineral or salt content of water, especially calcium, magnesium, sodium, chloride, sulfate, bicarbonate, and silica. These substances, if excessive, will affect machinery and industrial processes (by clogging pipes for example, or corroding switches), and their presence in water is frequently associated with discharge from industrial operations.

  TDS also affect the germination and growth of plants and the palatability of drinking water, though some minerals are desirable for their beneficial properties. Drinking water should not have more than 500 mg/L of TDS while irrigation waters may have up to 1,500 mg/L of soluble minerals.

  Hard waters contain so much calcium and magnesium that it is difficult to make soaps lather. When heated, hard water forms the scale or deposits that we see on cooking utensils and water pipes. Water softening solves the hard water problem but may increase the amount of sodium in the water — a possible danger to people on low sodium diets. Sodium in drinking water should be limited to about 20 mg/L.

  Total iron (suspended and dissolved) causes problems in water if it exceeds 0.3 mg/L. High iron levels impart a reddish brown color to water or a bad taste to cooked foods and may restrict growth in turkeys.

  Chlorides in water should not exceed 250 mg/L; otherwise, the water may have a salty taste. Excessive chloride levels may also indicate pollution from sewage or other sources.

Sulfates, which should not exceed 250 mg/L, are caused by the leaching of natural deposits of magnesium sulfate (Epsom salts) or sodium sulfate (Glauber's salt). These salts are undesirable because of their laxative effects.

Nitrates (NO_3-) and nitrites (NO_2-) pose health problems to animals and humans, including poultry. Their presence in surface or groundwater in large amounts may indicate septic tank failures, overfertilized fields, or other problems. Nitrate nitrogen levels in drinking water should not exceed 10 mg/L; and nitrites, which convert to nitrates, should not exceed 1 mg/L.

- Chlorine gas and other chlorine compounds are powerful disinfectants and oxidizing agents. Chlorine should be limited in drinking water to no more than 0.05 mg/L; however, there must be a small chlorine residual in public drinking water systems to assure that the water is disinfected.

- Dissolved oxygen (DO), which is vital for aquatic life, can be a key test for water pollution. At DO levels below 3 mg/L, fish may become stressed or die. Generally, in unimpaired waters, dissolved oxygen ranges from 7 to 14 mg/L. However, DO levels approaching 14 mg/L on sunny days may indicate high density algae growth and possible nutrient enrichment (pollution).

Usually, among these parameters, only pH, total iron, DO, and nitrates/nitrites have reference to poultry. Nevertheless, careful and complete monitoring of private water supplies and wells is a must because they provide drinking water for home and poultry operations. When the chemical properties of water exceed acceptable limits for intended uses, water quality is impaired.

Biological Properties

Private water supplies should also be tested once or twice a year for any sign of coliform bacteria. The test for fecal coliform bacteria can differentiate between the bacteria found in soils and plants and the bacteria found in warm-blooded animals. Common symptoms of coliform bacteria in humans are intestinal bloating and diarrhea.

Other bacteriological tests can identify many kinds and numbers of bacteria in water, but they do not separate harmful and harmless bacteria. Tests for Fecal Streptococci, Shigella, Salmonella, Staphylococci, and other bacteria may be necessary under certain circumstances. These tests are specific, time-consuming, and expensive. They isolate bacteria that cause typhoid fever, eye and ear infections, dysentery, boils, or other skin diseases. There are also tests for viruses, protozoa, and parasites.

In surface waters, aquatic vegetation and microscopic animal and plant life may be stimulated or retarded by various water quality factors — pH, nutrients (nitrogen and phosphorus), and turbidity, among others. But growth and decay cycles may have side effects that adversely affect water quality. Even helpful substances can become harmful in overabundance; for example, organic nitrogen in animal wastes and soils can cause "nutrient loading," which results in low DO levels and eutrophication (i.e., an overly productive waterbody.)

Physical Properties

Physical characteristics of water include turbidity, color, taste, odor, and temperature. The presence of foam is an indicator of dissolved organic substances, perhaps raw sewage. Suspended particles may cloud the water, and dissolved substances may alter its odor or taste. Turbidity or cloudy water may indicate the presence of suspended sediments, which reduce light penetration. Color affects quality and can be aesthetically displeasing. Taste and odors can result from dissolved metals, gases, organic materials, or chemicals.

Radiological Properties

Some radioactivity in water, food, and air is natural. However, if higher levels than usual are suspected, the appropriate state agencies should be notified.

Summary

Without efficient management of poultry waste and dead birds, poultry operations could become a source of excess nutrients, disease-caus-

ing bacteria or viruses, and dissolved substances in our nation's surface and groundwater supplies. Proper waste management will enhance the quality of water for everyone.

References

Palmer, E.L., J.J. Kolega, and R.S. Woodhull. 1972. Home Water Supply Treatment. Pamphlet. Reprint. Cooperative Extension Service, College of Agriculture and Natural Resources, University of Connecticut, Storrs, CT.

Shelton, T.B. 1971. Interpreting Water Quality Analysis: What Do the Numbers Mean? Cooperative Extension Services of the Northeast States. Cooperative Extension Service, Rutgers University, New Brunswick, NJ.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

WQI / 3 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Poultry Production and Water Quality

Every year, environmental issues seem to gain emphasis nationally and internationally as the importance of a cleaner environment and respect for pollution prevention practices receive increasing public support. The matter is most pressing to livestock and poultry producers because as environmental sophistication grows so does the focus on nonpoint source pollution. What is more, this deeper environmental sensitivity has occurred simultaneously with an extraordinary increase in the size of the poultry industry and its concentration in certain regions near processing and packing plants. The potential for adverse environmental impact appears greater as a result of the industry's trend to grow ever larger numbers of birds on smaller areas of land.

Understanding Animal Wastes and the Environment

Good waste management practices are essential for preventing the transport of sediments, nutrients, and bacteria into groundwater, rivers, and streams — that is, to prevent pollution — and to protect agricultural resources. The latter aspect of waste management ensures that growers will get the best return on their investments since animal waste is also a valuable resource, a collection of by-products that can be reclaimed for other uses.

The term "poultry waste" generally refers to manure: the feces and uric acid excreted by the growing birds; "litter," on the other hand, refers to manure and used bedding materials. Other wastes associated with poultry production include washwater, storm (and muddy) water runoff, and the carcasses of dead birds and spent hens. Processing wastes include other rendering and lagoon residuals.

These same materials, however, contain (1) valuable nutrients that can reduce the need for commercial fertilizers and increase plant yield; and (2) organic matter that can improve soil quality and extend its ability to hold water. Little wonder, then, that what happens to these by-products can be good or bad for the industry and for the environment.

On the one hand, poultry wastes can do a lot of good. They can be used as fertilizer, soil enhancers, cattle feed, or energy. Poultry producers can add value to these products — and prevent them from contaminating surface and groundwater — by using proven, acceptable methods of collection, storage and handling, treatment, disposal, and management. All such beneficial uses depend on proper management. Without such management, the value of the waste will decline rapidly, even as its potential for adversely affecting the environment and water quality steadily rises.

Pollution Is Not Inevitable

Poultry growers, whether their operation is consolidated or diversified need not produce any pollution outside the system. Pollution occurs only when litter is mismanaged — for example, when it is land applied in quantities that exceed plant needs, or when the ground is wet or frozen. As a result of such applications, potentially contaminating substances become "available" to the environment. If they also become "detached" from the site, for example, by being adsorbed to sediments or dissolved in water, they can be "transported" off site. Transport occurs when contaminants in the animal waste (the unused nutrients, bacteria or other elements in the litter) are released to surface drainage or infiltrate beneath the soil surface in groundwater recharge areas.

To control and prevent pollution, poultry growers need to understand how the value of such by-products can be enhanced and maintained. The value in poultry by-products and their potential to cause either point or nonpoint source pollution have the same origin. That is, the waste and dead birds contain nutrients and salts, suspended materials, the various products of biological reactions, and microorganisms. These elements can be beneficial to the grower, other farmers, the environment, or they can be harmful.

Nutrients and Salts

Poultry manure is a valuable nutrient for grain and fiber crops, forage crops, fruits, and vegetables. However, if manure, litter, dead birds (as compost or as buried carcasses), and/or wastewater are not properly protected and utilized, water contamination can occur from the release of excess nitrogen and phosphorus into the environment.

Nitrogen is an essential plant nutrient but, in excess, it can be harmful. High concentrations of nitrate in drinking water can affect human health, especially in infants and children. Ammonia in small quantities is toxic to fish and aquatic organisms; and high concentrations of nitrate in drinking water can also have significant effects on young chickens.

When nitrogen and phosphorus concentrations in waterbodies rise too high, algae and rooted aquatic plants take over, prematurely aging and choking the waterbody and creating undesirable conditions — odors, offensive taste, and discoloration — all of which can make the water unfit for consumption or recreational and aesthetic use. Further, these eutrophic conditions can kill fish, clog water treatment plant filters, and lead to the growth of blue-green algae, a species that can be fatal to livestock.

Because nitrate-nitrogen is highly mobile, it can leach into groundwater and flow with stormwater runoff into surface waters. If too much poultry manure and litter are used as fertilizer, nitrogen and phosphorus concentrations in nearby waters are likely to be high. Soil erosion also increases the amount of phosphorus in surface waters. Excessive phosphorus in soil, above 800 mg/L, may become soluble and move into groundwater. Phosphorus concentrations may vary, depending on the type of soil and its organic content.

Calcium and sodium salts are added to poultry feeds to help the birds maintain chemical balance and nutrition. Excess salts pass through the animals and are eliminated in manure. Sometimes, when the waste accumulates, the salts leach into groundwater and enter surface water through unprotected runoff. There they alter the water's taste or harm freshwater plants and animals.

Suspended Materials

When suspended matter from poultry wastes reach surface water, the waterbody not only looks unattractive — the quality of the water invariably suffers. The suspended material reduces the penetration of sunlight and therefore slows the production of oxygen. The result is an oxygen demand that reduces the levels of dissolved oxygen in the water. It also clogs fish gills, makes it difficult for sight-feeding fish to find food, and settles over fish spawning areas.

Products of Biological Reactions

In a natural environment, the breakdown of organic matter, such as poultry waste, is a function of complex, interrelated, and mixed biological populations. All substances of animal or vegetable origin contain carbon and are, therefore, organic. Organic matter is converted to simple compounds by naturally occurring microorganisms. These simple compounds may be other forms of organic matter or they may be nonorganic compounds or gases, such as nitrates, orthophosphates, ammonia, and hydrogen sulfide. A biological reaction occurs when manure or other organic matter is added to water and anaerobic or aerobic organisms begin the decaying process. Aerobic bacteria (oxygen requiring organisms) consume free oxygen and produce carbon dioxide gas. Under anaerobic conditions (without oxygen), methane, amines, and sulfides are produced.

Microorganisms

Desirable and undesirable microorganisms live in our environment. Animal waste is a potential source of some 150 disease-causing organisms or pathogens. These organisms include bacteria, viruses, fungi, protozoa, and parasites. Exam-

ples of undesirable microorganisms include Salmonella, Cryptosporidium, Giradia, Listeria, coliform, New Castle (virus), ringworm, coccidiosis, and Ascaris.

When found in water or wastes, these pathogens pose significant threats to humans and other animals. They can infect humans and animals through drinking water, contact with the skin, or consumption of fish or other aquatic animals. Most pathogens die relatively quickly. However, under the right conditions, they may live long enough to cause problems. They may persist longer in groundwater than in surface water.

Producers can prevent poultry by-products or waste from contaminating water. However, environmental needs and solutions are site specific and regional in nature. In some cases, state regulations and permitting requirements may be more stringent than federal regulations. Therefore, local sources of information, including industry associations, state departments of environmental protection and public health, and USDA Natural Resources Conservation Service and Cooperative State Research, Extension, and Education Service offices should be consulted about poultry waste or by-products that affect water quality.

References

Blake, J.P., J.O. Donald, and J.E. Hairston. 1990. Preventing Ground and Surface Water Contamination by Poultry Waste. DTP Circular 11/90-010. Alabama Cooperative Extension Service. Auburn University, Auburn, AL.

Goan, H.C., and J. Jared. 1991. Poultry Manure — Proper Handling and Application to Protect Our Water Resources. PB-1421. Tennessee Cooperative Extension Service, University of Tennessee, Knoxville.

Magette, W.L., and R.A. Weismiller. 1991. Nutrient Management for Water Quality Protection. BFS-3. Maryland Cooperative Extension Service, University of Maryland, College Park.

U.S. Department of Agriculture. 1992. Agricultural Waste Management Field Handbook, Part 651. Soil Conservation Service. Washington, DC.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

WQI / 4 — 9/98

POULTRY WATER QUALITY CONSORTIUM

5100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411

Tel: 423 855-6470 • Fax: 423 855-6607

Understanding Water Quality Regulations

As the poultry industry grows, so does concern for water quality, conservation, and environmental management. Growers have individual and civic reasons for caring: they are responsible with other human beings for the earth's environment, and they realize that they, their families and neighbors, and those who live in connecting watersheds, distant cities, even other countries — ultimately breathe the same air and drink the same water.

Pollution is intolerable whether it occurs on privately owned land and water, or travels many miles downstream or over mountains to other destinations. The arithmetic is simple: good environmental stewardship reduces the cost of water pollution, saves natural resources, and makes good neighbors.

Federal and State Statutes

Federal water quality laws and regulations administered by the U.S. Environmental Protection Agency (i.e., Clean Water Act, Safe Drinking Water Act, National Pollution Discharge Elimination System [NPDES] Permits) and the laws of each state make it illegal to discharge wastes of any kind to waters of the United States. That is, poultry waste cannot be collected, stored, or applied anywhere or in any manner that would likely result in water pollution.

In rare instances, the effect of combined federal and state regulations appears to create double jeopardy. Such situations (though they can be misused by the media or exploited to create controversy) can usually be swiftly resolved; however, compliance with environmental regulations requires careful planning and management. A rule of thumb is simply to assess one's whole operation from time to time (e.g., Farm*A*Syst assessments are self-administered, voluntary, and confidential) to ensure that no conditions arise on the farm that would put the grower at risk of violating water quality laws.

Because regulations differ and each state has its own enforcement procedures, poultry growers are well-advised to check with state and local agencies before production begins or systems change. Often the state's requirements are more stringent than federal requirements; however, growers in coastal zones may be subject to additional federal statutes as a result of the Coastal Zone Act Reauthorization Amendments of 1990. Industry organizations, agricultural research institutions, private and government agencies can help growers know, understand, and comply with the regulations in their area.

Point and Nonpoint Source Pollution

For management purposes, water pollution sources are divided into two groups or types. *Point source* pollution comes from a discrete man-made conveyance, such as a pipe, lagoon, ditch, or storage tank. *Nonpoint sources* of pollution are dispersed, harder to pinpoint, and cumulative. They include land uses or human activities that are potentially significant because they are common and widespread. Agriculture, mining, forestry, highway and other construction, septic tank, fieldline, and other waste disposal systems, and urban runoff are examples of potential nonpoint source pollution.

Some activities are regulated as point and nonpoint sources of pollution. For example, industrial or municipal utilities may operate treatment plants, which are point sources of pollution, but they may also be responsible to prevent further contamination from, or of

stormwater runoff, a nonpoint source of water pollution. Similarly, some livestock facilities may be regulated as point sources when they are collecting, storing or conveying facility wastewater and runoff; but once the manure or litter has been applied to the land, it is managed as a nonpoint source. Poultry growers must know how to manage point and nonpoint sources.

General Guidelines

Since the Clean Water Act was passed in 1972, concentrated animal feeding operations (CAFOs), including some large poultry houses, have been regulated as point sources of pollution. Federal law which the states administer through the National Pollutant Discharge Elimination System (NPDES) program forbids point source discharges, that is, the discharge of any pollutant or contaminant to "waters of the United States."

Thus, CAFOs, like other point sources, must obtain an operating permit which prohibits discharge except from lagoons during storm events greater than 24-hour, 25-year storms. The permit also specifies best management practices to protect surface water, including diverting off-site drainage around the facilities and designing appropriate storage facilities for manure and process-generated wastewater. Adequate runoff storage must be included in the design; lagoons or holding ponds must be sized to withstand a 25-year, 24-hour duration storm.

Nonpoint Source Prevention Practices

The extent of nonpoint sources has been more fully realized in the last decade, but they are usually assessed locally on a stream-by-stream basis and controlled by conservation or "best management practices" (BMPs). BMPs are routine activities that can be incorporated in animal and crop farming to conserve natural resources and protect air, soil, and water quality. They are structures or activities that reduce the potentially harmful effects of agricultural production.

State and local Guidelines

Most states now require (1) permits for the operation and construction of confined animal facilities whether current or planned, if the facility uses a liquid waste management system; and (2) that all livestock farmers plan their waste management and disposal system, especially as it concerns land applications. Whether these plans are written, kept on file, or simply in evidence on site, may depend on other circumstances.

The conditions pertaining to permits are not uniform across the states, but they usually provide specific guidance for operations at, under, or exceeding a certain size; establish setback distances for grower houses, lagoons, and waste management structures (to protect water and air quality and to limit any nuisances that might impinge on nearby homes or public buildings, such as schools and churches); buffer zones; and design specifications for new construction.

Land application requirements generally establish when and where applications can be permitted; for example, only at approved rates, and with nutrient management planning; not on frozen ground or when rain is expected on slopes greater than 15 percent, or on setbacks from public buildings and property lines. Typical setback distances for land applications are 100 feet from streams or ponds, sinkholes, wells, and water supplies, and 50 feet from any water lines or known agricultural drains.

Getting Help

A system of standard operating procedures or practices developed in accord with, or as part of, a "resource management plan, or "animal waste management system" recommended by the USDA Natural Resources Conservation Service (NRCS), will generally meet state and local requirements. The NRCS offers technical assistance to growers and often works with local soil and water conservation districts and state and local agencies to help farmers write suitable plans.

Such guidance augments the grower's own engineering and technical resources and makes it easier to adapt national conservation practices to regional conditions. It may also be possible that growers are eligible for cost-sharing. The USDA has used cost-share programs to encourage conservation over many years. Similar programs may now exist or are being developed.

The NRCS guidelines can be found in the Agricultural Waste Management Field Handbook (AWMFH) or Field Office Technical Guides (FOTG) which are reviewed and supplemented as needed. Supplements to the National Handbook and specifications prepared by the states are reviewed in NRCS field offices to ensure the consistency of new and emerging technologies and rules. The U.S. Environmental Protection Agency and the Cooperative Extension Service have also prepared guidance documents applying conservation practices.

Changing Attitudes

In the United States, regulations to control nonpoint source pollution are not the only driving force behind changing attitudes. Voluntary programs, public education, and financial incentives are more in tune with traditional values. Growers want to protect the environment, increase their efficiency, and enjoy a good public image.

Animal waste management practices can increase their return on investment and protect natural resources, especially if one's objectives are as clear as this simple waste management formula:

- prevent the generation of wastes where possible;
- recycle wastes that cannot be prevented;
- pretreat wastes to eliminate possible contaminants; and
- dispose of unusable wastes properly as a last resort.

Management commitment and awareness, scientific research and common sense, and in some cases, new installations and equipment are needed to protect the availability and quantity of our natural resources. The scope of the problem is global, national, and industrywide; cooperation among agencies, associations, and individuals speeds the development of technology and its transfer, and creates a participatory environment that encourages the search for solutions and fosters attitude changes.

Compliance Issues

Water quality legislation has teeth. Section 309 of the Clean Water Act establishes criminal penalties for failure to comply with the regulations. The threat of prosecution can be a first step in forcing compliance; the charges can range from minor infringements or negligent actions (lightly punished) to more serious charges of conscious violations and knowing endangerment. Knowing and willful endangerment and outright falsification are the most serious charges.

In short, point source wastewaters that leave a poultry house or plant must comply with the national effluent levels. A pretreatment program may be necessary. Some poultry operations have discovered that running their own pretreatment plants, though expensive, can be more efficient than other methods of compliance.

The U.S. Environmental Protection Agency now uses audits to determine how and why publicly owned treatment works are not in compliance. Recent regulations (in 40 C.F.R. Part 403) concern pretreatment:

- Pollutants that would interfere with the operation of the publicly owned treatment works or cause fire or explosive hazards are not permitted.
- No pH levels lower than 5.0 are allowed.
- Solid or viscous pollutants are monitored.
- High levels of biological oxygen demanding substances (BOD) are regulated as are oils, grease, and toxic gases.

The poultry industry should, therefore, take an active part in pretreatment programs.

Federal regulations are administered in most cases by the states, whose regulations and permitting requirements vary and may be more stringent than national regulations. Please consult local sources of information, including industry associations, state departments of environmental protection and public health, and USDA Natural Resources Conservation Service and Cooperative State Research, Extension, and Education Service offices, to ensure that your waste management activities comply with all regulations and ordinances.

References

Barker, J. C. 1993. Water Quality Nondischarge Regulations for Livestock Farms in North Carolina. North Carolina Cooperative Extension Service, North Carolina State University, College of Agriculture and Life Sciences, Raleigh, NC.

Bonner, J. 1993. You and Animal Waste Regulations. Cooperative Extension Service, Mississippi State University, Mississippi State, MS.

Carawan, R.E. 1992. Update on Federal Wastewater Regulations. Pages 84-101 *in* J.P. Blake, J.O. Donald, and P.H. Patterson, ed., Proceedings. 1992 National Poultry Waste Management Symposium. National Poultry Waste Management Symposium Committee. Auburn University Printing Service, Auburn, AL.

Gleichert, G.C., E.W. Brunton, and K. Whitmire. 1992. Corporate Management Commitment to Waste and Environmental Management. Panel. Pages 19-32 *in* Proceedings 1992 National Poultry Waste Management Symposium. National Poultry Waste Management Symposium Committee. Auburn University Printing Service, Auburn, AL.

33 U.S.C. §1251 et seq. (Title 33, Section 1251 of the U.S. Code is correlated to §101 of the Federal Water Pollution Control Act [1972]. It is entitled "Congressional Declaration of Goals and Policy.")

U.S. Department of Agriculture. 1992. Agricultural Waste Management Field Handbook, Part 651. Soil Conservation Service, Washington, DC.

U.S. Environmental Protection Agency. 1993. Management Measures for Agricultural Sources. Chapter 2 *in* Guidance Specifying Management Measures for Sources of Nonpoint Pollution in Coastal Waters. EPA-840-B-92-002. Office of Water. Washington, DC.

Wilson, L.J. 1990. Livestock Waste Control Programs of Ten Midwest And Western States. Photocopy of agency report. Iowa Department of Natural Resources, Des Moines, IA.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

WQI / 5 — 9/98

POULTRY WATER QUALITY CONSORTIUM

6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411

Tel: 423 855-6470 • Fax: 423 855-6607

Drinking Water Quality — Protecting Your Birds' Health and Performance

Drinking water for poultry and other animals, ourselves included, is an important dietary requirement — and an easy one to take for granted. Under normal conditions, poultry will consume twice as much water as food — two pounds of water (about a quart) for each pound of food, though this amount will vary seasonally and with the bird's age.

Water is not only a nutrient; it also softens food and carries it through the body, helps digestion and absorption, and cools the body as it evaporates through the bird's lungs and air sacs. Water helps animals remove waste, lubricates their joints, and helps maintain body temperatures. Further, water is used to deliver vitamins and vaccines (though vitamin dietary supplements are probably only needed during stress conditions). Water is a major component in blood and a necessary medium for many chemical reactions that help form meat and eggs.

Poor water quality, on the other hand, can retard growth, curtail egg production, or produce lower egg quality, even before it is readily apparent. In many cases, however, growers merely assume the security and quality of their water supply. This assumption, though it obviously fits our traditional experience, leaves the water untested until or unless it adversely affects the flock's health and performance.

Growers who carefully monitor feed consumption, egg production, temperature, ventilation, light intensity, and mortality as factors related to optimal production should pay similar attention to water quality and to how much water their birds actually consume. It is important to have the water tested from time to time.

Water varies greatly in its quality and potential for contamination — even from wells in the same county — and the quality can be altered by extremes in its content, such as pH, bacteria, hardness and varying amounts of naturally occurring elements. Some pollutants may have little effect on the birds. It is always possible, however, that factors that do not affect the birds in one environment — for example, poultry are relatively tolerant to nitrate — will in another. Thus, nitrate has been known to affect the birds' performance when it is present in water along with other contaminants such as bacteria. In such cases, when the proper treatment of water is begun, or changes are made in the source of the birds' drinking water, their health and performance quickly returns to its normal levels.

Similar single or aggregated effects have been discovered in the birds' reactions to other naturally occurring elements. Thus, feed conversion, for example, has been positively correlated to the presence of sulfate and copper concentrations in the water, and livability with potassium, chloride, and calcium. Body weight is positively influenced by drinking water hardness and dissolved oxygen, and negatively influenced by total bacteria and pH less than or equal to 6.0. Acidity (which is corrosive in piping) is usually maintained at normal levels in drinking water supplies, but some growers acidify water to help prevent bacteria.

Drinking water standards have been established for human consumption, but not for birds. It is safe to say, however, that a consistent source of high quality water is essential for the optimum performance that today's market conditions require. The following table can be used to determine poultry drinking water quality.

Table 1.—Drinking Water Quality Standards for Poultry.

CONTAMINANTS	AVERAGE LEVELS	MAXIMUM ACCEPTABLE	REMARKS
BACTERIA			
Total bacteria	0/mL	100/mL	0/mL is desirable
Coliform bacteria	0/mL	50/mL	0/mL is desirable
ACIDITY/HARDNESS			
pH	6.8–7.5	6.8–8.0	< 6.0 is undesirable; < 6.3 may degrade performance.
Total Hardness	60–180 ppm	110 ppm	< 60 is unusually soft; > 180 is very hard.
NITROGEN COMPOUNDS			
Nitrate (NO_3)	10 mg/L (NO_3–N)	25 mg/L	Levels of nitrate from 3 to 20 mg/L may affect performance.
Nitrite (NO_2)	0.4 mg/L (NO_2–N)	4 mg/L	—
NATURAL CHEMICALS			
Calcium (Ca)	60 mg/L	—	—
Chloride (Cl)	14 mg/L	250 mg/L	Even 14 mg/L may be detrimental if sodium level is higher than 50 mg/L.
Copper (Cu)	0.002 mg/L	0.6 mg/L	Higher levels of copper produce bitter flavor.
Iron (Fe)	0.2 mg/L	0.3 mg/L	Higher levels of iron produce bad odor and taste.
Lead (Pb)	—	0.02 mg/L	Higher levels of lead are toxic.
Magnesium (Mg)	14 mg/L	125 mg/L	Higher levels of magnesium have laxative effect. Levels > 50 mg/L may affect performance if sulfate level is high.
Sodium (Na)	32 mg/L	50 mg/L	> 50 mg/L of sodium may affect performance if sulfate or chloride is high.
Sulfate (SO_4)	32 mg/L	250 mg/L	Higher levels of sulfate have laxative effect. Levels >50 mg/L may affect performance if magnesium and chloride are high.
Zinc (Zn)	—	1.5 mg/L	Higher levels of zinc are toxic.

Source: Adapted from Carter and Sneed, 1987.

Observe the Birds' Drinking Habits

Water temperature and taste are important components of water quality. They make the water appealing (thereby ensuring that animals will not neglect to drink in sufficient amounts); and they also indicate other problems: the presence of contaminants (e.g., disease-causing organisms or toxic metals); an acidic imbalance, or too much sodium. While several elements can cause poor water quality, the interaction between elements is, as previously noted, more significant in water quality problems than the simple fact of their presence.

Thus, producers should be concerned if their birds' drinking water contains any of the following elements:

- high concentrations of bacteria, particularly coliforms;
- dissolved solids — organic, inorganic, or toxic elements;
- turbidity (i.e., the presence of material in suspension rather than in solution in the water); and
- unpleasant physical characteristics, such as bitter, hard, odiferous, cloudy (or tinted) conditions.

The presence of any of these characteristics is sufficient to warrant investigation and perhaps an improvement or change in the water supply to protect the flock's health, longevity, and production. The following elements, however, should be of particular concern:

- the presence of nutrients, especially nitrate and nitrite;
- high concentrations of sodium, chloride, and hydrogen sulfide (sulfur water);
- excess levels of iron and manganese;
- toxic elements, such as lead, selenium and arsenic;
- microbial contamination; and
- industrial chemicals or toxins.

Nevertheless, the most telling effects of poor water quality are generally caused by the presence of bacteria or minerals. Thus, high concentrations of bacteria or toxic elements in the water affect the normal physiological processes of the animal, resulting in inferior performance. High concentrations of minerals may have less effect on the animals unless or until they clog the water system, depriving the animals of water.

Qualities to look for include turbidity, taste, odor and color. Turbidity results from materials in suspension, for example, silt; clay, algae or organic matter. Turbid waters are unpalatable, and they clog the delivery system. Water should not taste bitter, sweet, salty, or sour, since such impressions are usually the effect of salts. Bitter tasting water may be contaminated by iron and manganese sulfates. Iron gives the water a reddish or brownish color; copper tends to turn the water bluish. On the other hand, the water may be clear without being safe. The presence of total dissolved solids is not visible in "clear" water.

Sulfur water smells too much like rotten eggs arising from the presence of hydrogen sulfide; hydrogen sulfide and iron will create the condition known as "black water." Since hydrogen sulfide is caused by bacteria, chlorination can help solve the problem. Sulfate is a laxative and therefore a cause of wet litter in poultry houses. Sulfate generally does not cause a similar odor in water.

Practice Good Maintenance and Sample the Water Supply

Baby chicks are 85 percent water, adults are 55 to 60 percent water and eggs are 66 percent water. Even a 10 percent loss of water can cause serious physiological disorders and a 20 percent loss can lead to death. Thus, maintaining a quality drinking water supply in each poultry house is important, and checking the drinkers for proper functioning should be a normal part of an operator's daily routine. In fact, water cleanliness techniques should evolve each time an equipment line is upgraded.

Bell-type drinkers, for example, can have a high level of bacteria, but growers can use chlorination to solve this problem provided that they discontinue chlorination in cases of heat stress. And, because chlorine also kills viruses, and vaccines, powdered milk should be run through the system ahead of vaccines. Discontinue water treatment 72 hours before water vaccination.

Some growers are using intermittent watering programs to help save water and improve the litter (by keeping it drier). This procedure provides plenty of water but prevents overconsumption and spillage. It is not generally recommended in summer or with nipple and cup waterers. The attempt to conserve water and litter by cutting back on the amount of water in the waterers, while yet allowing the birds to drink at any time is not as safe as the intermittent watering regime.

To test your water: collect samples either at the well source or at the point of entry into the house, use a clean quart plastic bottle and transport the sample to a diagnostic lab. To test the bacterial levels of the water, flame the faucet with a propane torch, then run a small amount of water to cool the faucet. Collect the sample in a sterile container, and if possible avoid taking the sample in the broiler house in which birds are present.

Consider the Experience of Other Producers

Several demonstration projects have been done to assess the effects of poor water quality on poultry production. While the data are not conclusive, they do show the correlation between poor water quality and inferior production.

A field study conducted in Canada sampled the water supply of 33 farms (involving layer, broiler, and turkey farms). The producers were surveyed regarding any health or other problems they may have experienced in the month prior to the sampling. The parameters tested included carbonates, bicarbonates, pH, chloride, fluoride, nitrate, nitrite, sulfate, magnesium, calcium, sodium, potassium, and phosphate. The analysis revealed several instances in which the producer's problems directly correlated with water quality impairments.

On an egg producing farm, for example, the producer reported a high incidence of diarrhea among the flock and severe problems with the egg shells. About 15 percent of the eggs had pin-sized holes in their shells. The water quality on this farm had higher levels of carbonates, bicarbonates, sodium, chloride, and pH than any other farm participating in the survey.

Research by R.E. Waggoner profiled in a January 1987 issue of *Poultry Digest* has also shown that changes in water quality can affect the birds' performance. A demonstration conducted at two similar broiler houses — one performing well, the other not performing well — successfully linked the different outcomes to differences in the water supply. When the water supply was tested, the water quality was "good" at house number 1 (as was its performance); but the water at house number 2 (with unsatisfactory performance) had high concentrations of sodium and bacterial contamination.

On the same farm, another two broiler houses were connected to different water sources. One was fed from an old well, the other from a well that had only recently been drilled. When birds raised in the house connected to the new well did not thrive as expected, this house was reconnected to the old well, and its performance improved. Thereafter, high concentrations of sodium and sulfate were found in the drilled well.

Simple water sanitation procedures can protect poultry's drinking water from contamination. Producers have different opinions about which cleaning technique is most effective, but no one disputes its necessity. Some producers use cleaning agents to remove scale and slime, to tie up minerals in the water, and flush medications from the lines. These measures are followed by sanitizers to kill bacteria and algae.

References

Anon. 1987. "Effects of Water Quality on Broiler Performance Examined." Review of T.L. Barton et al. 1987. *Feedstuffs*, March 9, 1987, p. 17.

Anon. 1988. Water Quality for Poultry: What does it Mean? *California Poultry Letter*. University of California Cooperative Extension, Berkeley, CA.

Barton, T.L., L.H. Hileman, and T.S. Nelson. 1987. A Survey of Water Quality on Arkansas Broiler Farms And Its Effect on Performance. Proceedings of the Twenty-First National Meeting on Poultry Health and Condemnations, University of Arkansas, Fayetteville, AR.

Bramwell. R.K. 1997. Good Clean Water Is Necessary for Birds to Stay Healthy. Poultry Times, September 22, pp. 27.

Carter, T.A. and R.E. Sneed. 1987. Drinking Water Quality for Poultry. PS&T Guide No. 42. Extension Poultry Science, North Carolina State University, Raleigh, NC.

Cunningham, P. 1997. Water Quality Linked with Broiler Performance. Poultry Times, Oct. 6, pp. 6-7.

Grizzle, J., T. Armbrust, M. Bryan, and A. Saxton. 1996. Water Quality I: The Effect of Water Nitrate and pH on Broiler Growth Performance. *Journal of Applied Poultry Research* 5:330-336.

———. 1997. Water Quality II: The Effect of Water Nitrate and Bacteria on Broiler Growth Performance. *Journal of Applied Poultry Research* 6:48-55.

———. 1997. Water Quality III: The Effect of Water Nitrate and pH on Broiler Breeder Performance. *Journal of Applied Poultry Research* 6:56-63.

K. Keshavarz. 1987. Proper Water Management for Poultry. *Poultry Digest* (January 1987): 19-22.

Runyan, C. and J. Bader. 1995. Water Quality for Livestock and Poultry. Guide M-112. College of Agriculture and Home Economics, New Mexico State University, Las Cruces, NM.

Waggoner, R., R. Good, and R. Good. 1984. Water Quality and Poultry Performance," in Proceedings AVMA Annual Conference, July 1984.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

WQI / 6 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300
5720 Uptain Road
Chattanooga, TN 37411
Tel: 423 855-6470
Fax: 423 855-6607

Environmental Impacts of Poultry Waste

Poultry raised for commercial purposes produce large amounts of manure which — unlike the manure of free range or pastured animals — is a collectible resource. It contains valuable plant nutrients and other chemicals that, if properly managed, can be returned to the land or processed for other uses. Therefore, anyone planning to undertake a confined animal feeding operation must give serious attention to the proper handling of manure and other waste products.

Factors influencing the choice of animal waste management systems begin with the type and size of the operation being contemplated, the grower's management skills and inclinations, the local environment, federal and state laws and regulations, and the effect of the proposed waste management plan on the operation's economic forecast. The importance of the choice increases in proportion to the volume and potential value of the residual materials.

For Voluntary Action

The National Farm Assessment Program (Farm*A*Syst) expanded from a 1991 pilot project in Wisconsin and Minnesota. It is funded by the USDA Cooperative State Research, Education, and Extension Service, the USDA Natural Resources Conservation Service and the U.S. Environmental Protection Agency.

A Farm*A*Syst checklist provides a simple way to identify (1) where a grower's management actions and environmental concerns intersect; (2) the degree to which current practices may be putting these vulnerable points at risk; and (3) strategic actions one can take to correct problems and reduce risk. The checklist, or self-assessment, is comprehensive but not lengthy; and it is completely private. Other Farm*A*Syst program materials explain practical management strategies and environmental regulations and how to find technical resources and financial help. Consult with local Cooperative State Research, Extension, and Education and NRCS offices for more information, access to the program, and technical support.

Concern for soil and water quality is the key to selecting a successful waste management plan, but criteria to be considered include the size of the operation, the economic consequences involved, and the growers' (and company's) personal management styles. The complexity of the system, whether it is dry or liquid, and the best management practices that can be used to minimize its effects on the environment are the subject of subsequent fact sheets in this series.

Begin with the Land/Water Interface

Whether the wastes or by-products that accompany poultry growouts are good or bad for the environment depends in large part on interactions between the activities of the producers and the ecosystem. Hence, planning efforts begin with an assessment of the farmstead's location in relation to rivers, lakes, ponds, ditches and sinkholes; the chemical and physical properties of the soil profile; the availability of agricultural land in the production area; and the possible effects of poultry production on the naturally occurring cycles of nitrogen and phosphorus.

Why Begin with Water

Agricultural activities, including — in some areas — mishandled or excessive poultry wastes, are a major source of nonpoint source pollu-

tion, although agriculture and forestry management are not the only sources. Crop production, pastures, rangeland, feedlots and other animal holding areas are agricultural sources of the U.S. waters assessed, 50 to 60 percent of the water quality problems in rivers and lakes and 34 percent of the waters in more urbanized coastal areas are impaired from agricultural sources. Bacteria, sedimentation, and nutrients are the leading pollutants.

Properly managing manure, controlling runoff, and nutrient management planning in conjunction with land applications will reduce or eliminate much of the proposed source of pollution and contribute to more productive farming. Most nonpoint source pollution problems can be controlled if growers know how nutrients and soil interact and plan accordingly.

Nitrogen, phosphorus, and potassium move through cycles on a farm. As nutrients, they go from crops to animals (in feed) to the soil (waste applications) and back again to other crops. If the cycle holds, everything works as it should. But too many nutrients already in the soil or too much waste applied to the land can move with the soil into surface water or through the soil into groundwater until their presence in the water reaches unacceptable levels, that is, is sufficient to impair water quality.



Figure 1.—The nitrogen cycle. Source: Pennsylvania State University, College of Agriculture. 1989. Groundwater and Agriculture in Pennsylvania. Circular 341. Reprinted with permission.

Nitrogen

Of the three major nutrients in poultry waste, nitrogen is the most complex and hence the most likely to contribute to environmental problems. Most of earth's nitrogen exists as nitrogen gas in the atmosphere (see Fig. 1). It can be transformed into inorganic forms by lightning or into organic forms by plants, such as soybeans, alfalfa, or clovers. Nitrogen can also be transformed into inorganic forms (commercial fertilizers) by energy intensive processes.

Most of the nitrogen found in animal wastes is organic nitrogen. A smaller amount of the nitrogen in litter is ammonium. Organic nitrogen can be mineralized or converted by soil bacteria into inorganic nitrogen, the form in which nitrogen is available to plants. Excessive organic and ammonium forms of nitrogen will be transformed in soil into nitrate nitrogen (that is, into water soluble nitrogen).



Figure 2.—Abbreviated phosphorus cycle.

Losses of nitrogen regardless of source (e.g., manure, commercial fertilizer, or municipal biosolids) from the cropping system can occur as a result of volatilization, surface runoff, and leaching. Surface runoff can move dissolved nitrogen (especially nitrate), ammonium nitrogen attached to eroding soil particles, and organic nitrogen contained in organic or plant residues into streams and lakes. Nitrates also move with the soil or leach through well-drained soils past the root zone into the groundwater supply.

High levels of nitrate can be toxic to human health, especially newborns. Nitrates reduce the blood's capacity to carry oxygen or cause internal suffocation. Scientists tell us that too much nitrate can affect the weight, feed conversion, and performance of poultry. Too much nitrogen in surface water makes the water less productive and may result in fish kills.

Phosphorus

Poultry wastes also contain significant amounts of phosphorus (see Fig. 2). Phosphorus, like nitrogen, is essential for plant and animal growth and also contributes to environmental problems. In fact, it seems to be the limiting factor in the huge algae blooms that make lakes unfit for swimming and ultimately deplete their oxygen supply, deadening the water and killing fish. Phosphorus has become a major cause of water quality degradation.

Phosphorus exists in either dissolved or solid form. Dissolved phosphorus usually exists as orthophosphates, inorganic polyphosphates, and organic phosphorus in the soil. Phosphorus in the solid form is referred to as particulate phosphorus and may be composed of many chemical forms. Particulate phosphorus comes in four classifications:

- adsorbed phosphorus, which attaches to soil particles;

- organic phosphorus, which is found in dead and living materials;
- precipitate phosphorus, which is mainly fertilizer that has reacted with calcium, aluminum, and iron in the soil; and
- mineral phosphorus, the phosphorus in various soil minerals.

Approximately two-thirds of the total phosphorus in soil is inorganic phosphorus; the remaining one-third is organic. Both forms are involved in transformations that release water-soluble phosphorus (which can be used by plants) from solid forms, and vice versa.

Phosphorus-laden soil or dissolved phosphorus can move via runoff into rivers, lakes, and streams, where it causes excessive plant and algae growth, which in turn depletes the dissolved oxygen content in the water. Phosphorus-enriched waters contribute to fish kills and the premature aging of the waterbody. In the end, the beauty and use of the waters are seriously curtailed. Even relatively small soil losses may result in significant nutrient depositions in the water.

Controlling soil erosion and proper land application of phosphorus-containing wastes will greatly reduce the amount of phosphorus in water. While not normally a great concern, care must also be taken to prevent soluble phosphorus from leaching into groundwater.

Applying poultry waste to land at rates based on supplying the nitrogen needs of grain or cereal crops can lead to a phosphorus buildup in the soil. Planting forage crops in rotation with grain crops will help remove excess phosphorus. Maintaining soil pH at the recommended level is also an effective and economical practice for maximizing phosphorus efficiency. Crops use phosphorus most efficiently when the soil pH is between 6.0 and 7.0.

Soil phosphate levels are an important consideration in calculating poultry litter application rates. Land applications should be made only to soils that do not already contain excessive phosphate levels. An analysis or test should be conducted on each waste source prior to land application to determine proper phosphorus application rates.

Potassium

Potassium in poultry waste is a soluble nutrient equivalent to fertilizer potassium. It is immediately available to plants when it is applied. Potassium is fairly mobile but does remain in the soil to help supply plant needs, for example, strong stems, resistance to disease, and the formation and transfer of starches, sugars, and oils. Excessive amounts of potassium can inhibit or restrict the growth of some plants at certain stages of development. Small amounts of potassium may be leached to groundwater, especially in sandy soils; however, potassium or potash is usually not a threat to water quality or considered a pollutant.

Heavy Metals and Trace Elements

Heavy metals and trace elements, such as copper, selenium, nickel, lead, and zinc, are strongly adsorbed to clay soils or complexed (chelated) with soil organic matter, which reduces their potential for contaminating groundwater. However, excessive applications of organic waste containing high amounts of heavy metals or trace elements can exceed the adsorptive capacity of the soil and increase the potential for groundwater contamination. Excessive application of some heavy metals, for example, copper can be toxic to plants whose growth is needed to take up other nutrients.

Surface water contamination is a potential hazard if poultry wastes are applied to areas subject to a high rate of runoff or erosion.

Salts

Dissolved salts, mainly sodium, in high concentrations interfere with plant growth and seed germination, and may limit the choice of plant species that can be successfully grown. Poultry waste with low salt content and a high carbon to nitrogen ratio can improve soil water intake, permeability, and structure.

Using Litter Nutrients Wisely

High nitrate levels in groundwater and high phosphorus levels in surface water may be an indication that too much litter or fertilizer is being applied on too little land. Yet the fact that poultry litter is high in nutrients is precisely its value. The nutrients in this resource make it an excellent soil conditioner and fertilizer. Growers can maximize the benefits of having this re-

source and help protect their local water resources from high nutrient levels by planning and operating an effective nutrient management system.

Application practices will vary with the area's cropping practices, topography, and other environmental and economic conditions. Waste and soil testing are the simplest and most important aspects of nutrient management. They help farmers monitor the nutrient supply to guarantee that it is adequately controlled to produce the best crop yields and maintain water quality. When properly recycled, nutrients are not wastes but opportunities to improve the overall farming operation.

References

Bandel, V.A. 1988. Soil Phosphorus: Managing It Effectively. Fact Sheet 513. Cooperative Extension Service, University of Maryland, College Park.

Carter, T.A., and R.E. Sneed. 1987. Drinking Water Quality for Poultry. PS&T Guide No. 42. Cooperative Extension Service, North Carolina State University, Raleigh.

Fulhage, C.D. 1990. Reduce Environmental Problems with Proper Land Application of Animal Wastes. WQ201. Cooperative Extension Service, University of Missouri, Columbia.

Goan, H.C., and J. Jared. 1991. Poultry Manure — Proper Handling and Application to Protect Our Water Resources. PB 1421. Cooperative Extension Service, University of Tennessee, Knoxville.

Keeney, D.R., and R.F. Follett. 1991. Overview and Introduction. Chapter 1. *In* Managing Nitrogen for Groundwater Quality and Farm Profitability. Proceedings. Soil Science Society of America, Madison, WI.

Killpack, S., and D. Buchholz. 1991. What Is Nitrogen? WQ251. University Extension, University of Missouri, Columbia.

U.S. Department of Agriculture. 1992. National Engineering Handbook 210, Part 651. *In* Agricultural Waste Management Field Handbook. Soil Conservation Service, Washington, DC.

U.S. Environmental Protection Agency. 1995. The National Water Quality Inventory: 1994 Report to Congress. EPA841-R-95-005. U.S. Government Printing Office, Washington, DC.

Wells, K.L., G.W. Thomas, J.L. Sims, and M.S. Smith. 1991. Managing Soil Nitrates for Agronomic Efficiency and Environmental Protection. AGR-147. Cooperative Extension Service, University of Kentucky, Lexington.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 1 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6807

Planning Poultry Waste Management

Poultry litter is a valuable by-product of the poultry industry. It is, for example, a natural soil amendment — a source of nutrients and organic matter that can increase soil tilth and fertility. If it is mishandled, it is also a potential pollutant of surface and groundwater.

Developments within the poultry industry and increasing restrictions or regulations on the disposal of poultry waste have significantly altered the industry's attitudes about this immense resource. Broiler operations alone produced over 15.2 billion pounds of litter in 1996, and because production is concentrated in very small geographic areas, waste management planning is extremely important.

Historically, poultry growers applied poultry waste to their farms as much to dispose of the material as to use it for fertilizer. Difficulties with this practice increase with the supply for several reasons:

- Less cropland is farmed than 20 years ago, and more poultry operations exist than in the past.
- Typically, more nutrients are brought onto the farm in the form of feed than leaves the farm in the form of meat or eggs. The nutrients left on the farm are in the manure and bird mortalities.
- Other resources (wastewater, composted residential waste, and sludge) are also being used for land applications, which increases competition for the remaining croplands and pastures.
- We know now that valuable nutrients — nitrogen, phosphorus, and potassium — are squandered and water resources are threatened if land applications of waste are overdone or misapplied.
- Regulations regarding waste management are now enforced by many states.

Increasingly, concern for water quality has become a major catalyst for the upsurge of interest in new approaches to land application. Today's growers are finding that they can no longer afford to dismiss the benefits of poultry waste planning, which include increases in farm production, environmental protection, and lower costs.

Plan Components

The waste management system must provide for the collection, storage, and final distribution (use) of manure and dead birds in an environmentally safe way. State laws generally do not permit direct discharges of animal waste into water, and many states require permits for confined animal operations beyond a certain size. Soil and water quality considerations are the key to choosing among types of waste management systems (for example, whether to install a dry or liquid system).

Components will depend on the operation's size, operating plan, and the producer's access to technical expertise. For example, one facility may have an incinerator for handling dead birds; another may have an incinerator and a composting facility.

Components of waste management systems include, but are not limited to, the following:

- composting facilities;
- debris basins;
- dikes, diversions, and fencing;
- filter strips and grassed waterways;
- transportation and other heavy use area protections and equipment;



Figure 1.—Representative components of a poultry waste management system.

- irrigation schedules and equipment;
- nutrient management planning, including soil and manure testing procedures;
- pond sealings or linings;
- subsurface or surface drains, or both; and
- waste storage ponds, other storage structures, and treatment lagoons.

The relationship among these components is shown in Figure 1. Note that the drawing contains a broiler house and several examples of caged layer houses. Figure 2 shows the six stages of animal waste management.

An Integrated Approach

Traditionally, poultry growers have efficiently disposed of litter as soon as possible by spreading the manure or litter on croplands or pasture. Now growers must begin their waste



Figure 2.—Steps in an animal waste management planning system.

management inside the poultry house. Along with the objectives of flock health, production, and odor control, today's waste management planning must also protect water quality and contribute to a profitable farm operation. Integrating these broad objectives requires growers to develop other options in addition to land application.

Thus, to be profitable and to protect our natural resources — air, soil, water, plants, and animals — poultry growers must plan their waste management practices carefully. They must base application rates and timing on soil test results and crop removal needs along with an analysis or estimate of the nutrients contained in the manure or litter.

Poultry waste management planning begins before actual production and may have as many as six steps or functions (Fig. 2). The first step is to understand the waste management process. What are these wastes? How much does a particular operation produce on an annual basis? Where or how can these wastes be used? The second step, once the quantity and quality of the wastes have been determined, is to put efficient collection methods in place.

The third and fourth steps are to have adequate storage facilities and the ability to transfer or move the waste from the point of collection to the appropriate point of use. In some cases, a fifth step is included to determine whether biological, physical, or chemical treatment of the wastes is needed to reduce the potential for pollution or to prepare the wastes for final use.

The sixth and final step in the waste management plan is to use the wastes — normally, for land application as a fertilizer and soil improvement or as a feed ingredient — in accordance with the nutrient management plan. Growers will usually have identified sufficient land on which to apply the waste before production begins. If enough land does not exist, other uses must be assigned or additional lands located for disposal.

The Benefits of Nutrient Management

Nutrient management actually begins when the poultry waste process has proceeded from collection and conservation to the actual use of these products for land applications or energy and feed production. Nutrient management planning matches the nutritional requirements of the soils, crops, or other living things with the nutrients available in the manure or litter, thereby preventing nutrient imbalances, health risks, and surface and groundwater contamination.

Nutrient value is based on the nitrogen, phosphorus, and potassium content of poultry waste. This value can be enhanced by matching the nutrients available in the resource with the nutrients needed in the application. This planning also reduces disposal and handling costs. Nutrient management planning makes it possible to use poultry manure to replace commercial fertilizers or at least to reduce their use — thereby reducing some costs of crop production. Nutrient management also minimizes the potential harmful effects that overapplication can have on the environment.

An essential goal of nutrient management is to make sure that any poultry waste, especially manure or litter, is used safely and effectively. Nutrient management is, in fact, the key to using this waste as a beneficial by-product. To obtain maximum benefit and prevent possible contamination of surface and groundwater, the following management principles and practices can be applied:

- Develop and apply a Resource Management System, an Animal Waste Manage-

ment System, a Nutrient Management Plan, or similar program. Assistance is available from the local offices of the U.S. Department of Agriculture's Natural Resources Conservation Service, the Cooperative State Research, Extension, and Education Service, state departments of agriculture, or soil and water conservation districts.

- Find out if your state uses nitrogen as a basis for land application requirements. If not, is phosphorus a concern in your area?
- Analyze poultry waste regularly to monitor major nutrients and pH levels. Proper soil pH will help maximize crop yields, increase nutrient use, and promote decomposition of organic matter.
- Apply only as much fertilizer (nutrients) as the crop can use.
- Calibrate equipment and apply waste uniformly.
- Incorporate poultry waste into the soil if possible to reduce runoff, volatilization, and odor problems.
- Do not spread poultry waste on soils that are frozen or subject to flooding, erosion, or rapid runoff prior to crop use.
- Spread poultry waste during specific growing seasons or as scheduled for maximum plant uptake and to minimize runoff and leaching.
- Use proper storage methods prior to land application.
- Maintain a vegetative buffer zone between the field of application and adjacent streams, ponds, lakes, sinkholes, and wells.
- Follow approved conservation practices in all fields.
- Be considerate of neighbors and minimize conflicts when transporting or land applying poultry waste.

Training, technical assistance, and in some cases, financial aid are available to help growers and crop farmers identify problems and develop solutions for using poultry waste in their specific regions. The Natural Resources Conservation Service and Cooperative Extension Service have developed work sheets for animal waste management systems that help growers estimate production, obtain soil and manure analyses, and make economical and practical use of the organic resources generated on the farm. These agencies and others can help growers design facilities and develop overall resource management plans.

References

Bell, D. 1982. Marketing Poultry Manure. University of California, Cooperative Extension, Riverside.

Cabe Associates, Inc. 1991. Poultry Manure Storage and Process: Alternatives Evaluation. Final Report. Project 100-286. University of Delaware Research and Education Center, Georgetown.

Department of Natural Resources and Environmental Control. 1989. Poultry Manure Management: A Supplement to Delaware Guidelines. Cooperative Bulletin 24. Delaware, Cooperative Extension. University of Delaware, Newark.

Donald, J.O. 1995. Broiler Waste Management Planning. Circular ANR-926. Alabama Cooperative Extension Service, Auburn University, Auburn, AL.

Fulhage, C. 1992. Reduce Environmental Problems with Proper Land Application of Animal Wastes. WQ201. University Extension, University of Missouri, Columbia.

Margette, W.L., and R.A. Weismiller. 1991. Nutrient Management for Water Quality Protection. Bay Fact Sheet 3. Cooperative Extension Service, University of Maryland, College Park.

Missouri Department of Natural Resources. 1993. Obtaining a DNR Letter of Approval for a Livestock Waste Management System. WQ217. University Extension, University of Missouri, Columbia.

Swanson, M.H. No date. Some Reflections on Dried Poultry Waste. University of California Cooperative Extension, Riverside.

U.S. Department of Agriculture. 1991. Improving and Protecting Water Quality in Georgia . . . One Drop at a Time. Soil Conservation Service, Athens, GA.

U.S. Department of Agriculture. 1991. Improving water quality by managing animal waste. SCS.WQ3 *in* Water Quality and Quantity for the 90's. Soil Conservation Services, Washington, DC.

———. 1992. National Engineering Handbook 210, Part 651, *in* Agricultural Waste Management Field Handbook. Soil Conservation Service, Washington, DC.

U.S. Environmental Protection Agency. 1993. The Watershed Protection Approach: A Project Focus. Draft. Assessment and Watershed Protection Division. Washington, DC.

Zublena, J. 1993. Land Applications: Nutrient Management Plan. Presentation. Poultry Waste Management and Water Quality Workshop. Southeastern Poultry and Egg Association, Atlanta, GA.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 2 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Dry Waste Management

A well-planned waste management system will account for all wastes associated with a poultry agricultural enterprise throughout the year, from the production of such wastes to their ultimate use. The more integrated the waste management system is with the grower's other management needs, such as production, marketing, pest control, and conservation, the more profitable the farm will be.

The best method for managing poultry manure depends on the type of growing system (open range or enclosed housing), dry or liquid collection, and the way the house is operated. Misuse of poultry manure can reduce productivity; cause flies, odor, and aesthetic problems; and pollute surface and groundwater. Poultry manure can produce dust and release harmful gases such as carbon dioxide, hydrogen sulfide, methane, and ammonia. Fresh manure is troublesome if it gets too wet.

Poultry wastes are handled differently depending on their consistency, which may be liquid, slurry, semisolid, or solid. The total solids concentration of manure depends on the climate, weather, amount of water consumed by the birds, type of birds produced, and their feed; it can be increased by adding litter or decreased by adding water.

Within the poultry industry, broiler, roaster, Cornish hen, pullets, turkey, and some layer operations are dry; live bird processing, some layer, and most duck and goose operations are liquid. In most dry operations, the birds are grown on floors covered with bedding materials. The manure collected from ducks, geese, and large high-rise layer operations is usually pure or raw manure, unmixed with litter though it may be mixed with water during cleanout.

Open Range or Enclosed Housing

Fields, pastures, yards, or other outdoor areas are used as ranges for chickens, turkeys, ducks, or game birds. Such areas must be located and fenced so that manure-laden runoff does not enter surface water, sinkholes, or wells. Unless these areas are actually feed lots (confinement areas that do not support vegetation), no collection and storage of manure is required. Instead, the manure is recycled directly to the land. Best management practices, such as pasturing the animals away from sinkholes and other water resources, and preventing animal access to streams, apply to these operations. In confinement operations, by contrast, the manure is collectible and can become a valuable coproduct of the operation.

In enclosed settings, dry and liquid wastes require different collection, storage, handling, and management systems. The management of dry manure depends primarily on how it is stockpiled or stored from the time of its production (at cleanout) until it is properly land applied. The following paragraphs describe general house conditions that affect the production and quality of this material and the principles of dry waste management. Liquid waste management is explained in an additional fact sheet contained in this handbook (PWM-4).

Kinds of Poultry Waste — Manure and Litter

Livestock manure is feces and urine; poultry waste is manure with added bedding or water. The only way to know for certain its quantity, concentration and composition is from lab analysis. The amount of manure a given flock produces can be estimated from the amount of feed the birds eat. Roughly 20 percent of the feed consumed by poultry is converted to manure. Manure mixed with a



Figure 1.—The broiler litter highway: broiler litter generated in 1996, in the United States.

water. The only way to know for certain its quantity, concentration and composition is from lab analysis. The amount of manure a given flock produces can be estimated from the amount of feed the birds eat. Roughly 20 percent of the feed consumed by poultry is converted to manure. Manure mixed with a bedding material is called litter, and its constituent properties vary, depending on how the chickens are fed and their age and size.

Other conditions that affect litter's quality include the age and type of the bedding material, excessive moisture, frequency of cleanouts, and subsequent storage conditions. The constituents of the litter can be estimated from prior analyses of similar wastes, but all litter should be analyzed at least once a year until its nutrient value is firmly established (after that, it may be tested less frequently, perhaps every two or three years unless management practices change).

The volume of litter varies widely, depending on the producer's management style. Indeed, many of the same conditions that determine the litter's makeup also affect its quantity. For example, the feedstock, number of cleanouts, climatic conditions, and bird genetics are all factors. Broilers, however, produce as much as two pounds of litter per bird or about one ton per year per 1,000 birds: about 81 cubic feet of litter for each 1,000 birds.

In 1996, nearly 15.2 billion pounds of litter were produced by broiler operations in the United States — enough to cover 1,619 miles of a two-lane highway to a depth of three feet. This estimate is from the USDA National Agricultural Statistics Service, and the "litter highway" can be imagined as the distance from New Orleans, Louisiana, to Chicago, Illinois, and on to Fargo, North Dakota (Fig. 1).

That much litter can and must be responsibly used. Bedding materials, manure, and used

erals in broiler litter include calcium, magnesium, sulfur, sodium, iron, manganese, zinc, and copper.

Table 1.—

LITTER PRODUCED PER 1,000 BIRDS	
2 lb bird	0.45 ton per cycle
4 lb bird	1.0 ton per cycle
6 lb bird	1.5 ton per cycle
AVERAGE NUTRIENT CONTENT OF BROILER LITTER	
nitrogen	60 lb per ton
P_2O_5	55 lb per ton
K_2O	45 lb per ton

Management Practices

Litter should be kept from becoming overly wet. In a well-managed house, the moisture level in litter will range from 25 to 35 percent. Higher moisture levels increase its weight and reduce its nitrogen value. Litter that does not become saturated can be left in the house between flocks. However, cake (litter that is saturated with water) must be removed from the house between cleanouts to protect the remaining litter. After its removal, the cake should be dried to prevent odor, precautions should be taken to prevent groundwater contamination, and stormwater should be diverted from contact with the litter.

If cake is properly removed from the house, total cleanouts can be delayed — sometimes for an entire year. Checking for water leaks in the house and keeping the house at an even temperature are management practices that reduce the production of cake. The total weight and volume of litter will depend on the type of bedding material used, its depth, whether cake is present or removed, and the length of time between cleanouts. Its quality also depends on how it is removed from the house, whether the floor is raked or stirred between flocks, and how it is stored.

Manure is dried by aerating it using some form of ventilation. Ventilation can be achieved naturally (through proper housing design) or mechanically (through equipment). Aeration should produce a low odor product with about 15 to 25 percent moisture. Because it has less odor and weight, it is less expensive to haul, contains more nutrients, and is easier to store.

Dry Waste Storage Facilities

Common procedures for managing dry broiler litter or dry manure from layer operations center on protecting this material after it is removed from the house until its valuable fertilizer nutrients can be put to other uses. Litter that is not properly stockpiled or stored suffers a reduction of nitrogen from releases to air and water. These losses represent both lost income and the potential for surface and groundwater contamination. To prevent such losses, facilities used for storing dry poultry waste should meet or exceed the following conditions:

- a sufficient capacity to hold the waste until it can be applied to land or transported off the farm,
- adequate conditions of temperature and humidity to permit storage of the waste until it is needed,
- a concrete or impermeable clay base to prevent leaching to groundwater,
- appropriate roofing, flooring, and drainage to present rainfall, stormwater, runoff, and surface or groundwater from entering the waste,
- a location that prevents runoff to surface waters or percolation to groundwater, and
- ventilation and containment for effective air quality and nuisance control.

The ideal storage design is a roofed structure with an impermeable earthen or concrete floor. This design keeps the litter dry, uniform in quality, and easy to handle, and it also minimizes fly and odor problems. Management plans that allow for proper storage achieve the following:

- save water,
- improve bird quality,
- improve the production environment,
- reduce the amount of ammonia released from litter,
- reduce the volume of cake,

- extend the time between cleanouts,
- increase the product's value and flexibility, and
- protect the quality of adjoining waters.

Kinds of Storage Facilities

Generally, storage facilities can be open, covered, or lined (permanently lined, in some cases); or they can be bunkers or open-sided buildings with roofs. Perhaps the most common facilities for collecting and storing poultry litter include floors, pits, dry-stack buildings, or covered outdoor storage facilities with impermeable earthen or concrete flooring.

Floor Storage

Most broiler, roaster, Cornish hen, pullet, turkey, and small layer operations raise birds on earthen or concrete floors covered with bedding material (Fig. 1). A layer of wood shavings, sawdust, chopped straw, peanut or rice hulls, or other suitable bedding material is used as a base before birds are housed. Wet litter — that is, cake — is removed after each flock. A complete clean-out can be done after each flock or once every 12 months or longer, depending on the producer's requirements. Slat or wire floor housing, used mainly for breeder flocks, can be handled the same way. Floor storage is the most economical method to store litter. Care must be taken not to leave foreign material such as wire, string, light bulbs, plastic, or screws in the litter.

Dry Stack Storage

Temporary storage of litter in a roofed structure with a compacted earthen or concrete floor is an ideal management method (Fig. 2). Large quantities of waste can be stored and kept dry for long periods of time. To prevent excessive heating or spontaneous combustion of wastes, stacks should not exceed 5 to 8 feet and large variations in moisture content should be avoided. Dry stacks promote ease of handling and uniformity of material; in addition, disposal is relatively easy. Dry stacks protect the resource from bad weather and make it available for distribution at appropriate times.

A variation on this option is a stack or windrow located in an open, well-drained area and protected from stormwater runoff. The stack must be covered with a well-secured tarpaulin or other synthetic sheeting.



Figure 1.—Two types of litter-floor poultry houses.



Figure 2.—An ideal dry stack storage facility is a roofed structure with an earthen or concrete floor.

Storage in covered or uncovered facilities is not the only alternative. Field storage on the farm, applicator storage (that is, storage by the crop farmer who will use the litter or manure for fertilizer), cooperative storage (several growers sharing a larger facility off-site), and private storage (by entrepreneurs who will sell or process the litter to create new products) are additional methods of waste storage. Each method must be evaluated in terms of cost, environmental safety, and industry and regulatory practice.

In some states, permits may be required for a storage facility or for other parts of your resource management system. Possible zoning restrictions may also influence your choice of storage systems.

Proper storage is essential to optimize the waste's fertilizer value for crops, provide ease of handling, and avoid groundwater or surface water contamination. Consider also the feasibility of processing alternatives. Waste can be

- composted and pelletized to produce soil amendment and fertilizer products,
- converted to feed for beef cattle or to briquettes for fuel, or
- deposited in lagoons for anaerobic digestion and methane production.

Above all, use soil and manure testing to improve the success (crop yields) and timing of land applications. Practice biosecurity (that is, safeguard the application from disease causing organisms and fly larvae) at all times.

Using poultry litter as a feed supplement for cattle has become popular. Methods of waste handling and storage can greatly affect the quality of the material as a feed ingredient. Litter with the highest nutritional value for refeeding is found in the upper layers of the litter pack. Large amounts of soil increase the ash content and reduce the nutritive value of litter. Feed litter should be deep stacked at least three weeks to ensure that sufficient heat is generated to kill pathogens.

Remember: The use of manure storage structures is a best management practice for the protection of environmental quality, and an interim step in waste management planning. It should be followed by nutrient management planning and appropriate use of the litter for land application.

References

Brodie, H.L., L.E. Carr, and C.F. Miller. 1990. Structures for Broiler Litter Manure Storage. Fact Sheet 416. Cooperative Extension, University of Maryland, College Park.

Boles, J.C., K. VanDevender, J. Langston, and A. Rieck. 1993. Dry Poultry Manure Management. MP 358. Cooperative Extension Service, University of Arkansas, Little Rock, AR.

Boles, J.C., G. Huitink, and K. VanDevender, 1993. Utilizing Dry Poultry Litter — An Overview. FSA 8000-3M-7-95R-S563. Cooperative Extension Service, University of Arkansas, Little Rock, AR.

Cabe Associates, Inc. 1991. Poultry Manure Storage and Process: Alternatives Evaluation. Final Report. Project Number 100-286. University of Delaware Research and Education Center, Georgetown.

Department of Natural Resources and Environmental Control and Cooperative Extension Service. 1989. Poultry Manure Management: A Supplement to Delaware Guidelines. University of Delaware, Newark.

Donald, J. 1990. Litter Storage Facilities. DTP Circular 10/90—004. Alabama Cooperative Extension Service, Auburn University, Auburn, AL.

Donald, J.O., and J.P. Blake, F. Wood, K. Tucker, and D. Harkins. 1996. Broiler Litter Storage. Circular ANR-839. Alabama Cooperative Extension Service, Auburn and Alabama A&M Universities, Auburn, AL.

Georgia Soil and Water Conservation Commission. 1994. Planning Considerations for Animal Waste Systems for Protecting Water Quality in Georgia. In cooperation with USDA Natural Resources Conservation Service and U.S. Environmental Protection Agency, Athens, GA.

Payne, V.W.E., and J.O. Donald. 1991. Poultry — Waste Management and Environmental Protection Manual. Circular ANR-580. Alabama Cooperative Extension Service, Auburn, AL.

Vest, L., and B. Merka. 1994. Poultry Waste: Georgia's 50 Million Dollar Forgotten Crop. I-206. Cooperative Extension Service, University of Georgia College of Agricultural and Environmental Science, Athens, GA.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 3 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

LIQUID WASTE MANAGEMENT

Ducks, geese, and some layer operations are usually handled through liquid waste management systems, though water greatly increases the amount of waste to be processed. In liquid waste management systems, collection and storage are generally combined in one operation, and in facilities that include pits, settling tanks, and earthen storage ponds, or lagoons. Sometimes additional treatment is used to convert its nutrient and mineral content to more stable products.

Volume comparisons between liquid and dry manure show that 10,000 caged layers produce nearly 2,500 pounds of manure per day, with an estimated volume of 50 cubic feet. In dry form, this manure weighs about 695 pounds, with 10 percent moisture, and reaches a volume of 27 cubic feet. This difference not withstanding, liquid waste management systems can be easier to automate and less labor intensive than dry waste management.

Constraints on the management system appear to be greater when the system is liquid:

- the pond or other holding facility must be emptied immediately when it is filled — the grower has less flexibility for scheduling land applications;
- if the waste storage structure is not properly designed and sealed, its contents may leach to groundwater or overflow into ditches, agricultural drains, or other surface water resources;
- toxic gases or unpleasant odors can occur in liquid waste, particularly when it is agitated or stirred;
- flies may find the manure storage ponds attractive breeding grounds, especially if they are improperly managed; and — a more important consideration —
- nearly all states have clean water laws that prohibit wastewater discharges to surface waters and groundwater recharge areas. Therefore, nearly all animal operations that have a liquid waste management system must have formal or informal permits to comply with these laws, even if they are not required to file for federal National Pollution Elimination Discharge System permits.

By contrast, solid waste systems are perceived to have less environmental risks; and with less volume to control, they may also have lower equipment and energy costs. These considerations — and operator preference — may help growers decide between dry and liquid waste management systems.

Lagoon flush systems were a source of environmental and public relations problems (e.g., spills and odors) during heavy rains in 1995 and 1996. If such problems persist, growers and researchers are likely to combine the best features of liquid and dry systems to find more protective and efficient methods of waste management. Researchers in Georgia have already modified a flush-type system beneath a caged layer line to accommodate a deep litter composting system. Plywood boxes containing plywood shavings are placed under the cages to collect the manure, which is turned twice weekly to promote composting.

Liquid Collection Methods — Pit Storage

Layers or pullets are often raised in cages arranged in two to four decks. The manure falls directly into a pit or is scraped into the pit from intervening dropping boards. Pits must be cleaned regularly, and the manure stored in concrete or steel storage tanks or applied directly to the land. A lagoon may be necessary to catch overflow. Ventilation fans are essential to

keep the manure dry, and reduce toxic gases, fly problems, and offensive odors.

There are three basic pit designs:

▼ **Shallow-pit systems**, built of concrete at ground level, are 4 to 8 inches deep and located 3 to 6 feet below the cages. Manure is scraped from the pit or flushed out with water and collected in a storage area or loaded directly into a spreader (Fig. 1).

▼ **Deep-pit systems** are usually 4 to 8 feet wide and may extend 2 to 6 feet below ground level with the cages at least 8 feet above the concrete or masonry floor. The pit floor and sidewalls must be sealed and thoroughly protected from stormwater runoff and groundwater seepage. Foundation drains and external grading are needed to remove subsurface water and to drain surface water away from the building.

▼ **High-rise systems** are similar to deep-pit systems but are built entirely aboveground. The cages are 15 to 30 feet above the ground (Fig. 2). The pit floor should be concrete and graded, with foundation drains. The water supply must be controlled if the wastes are retained in place for extended periods. If outside water penetrates the system and breaks out the side board, the manure can develop a serious fly problem or leach nutrients to groundwater.

Settling Tanks

Concrete, concrete block, or steel storage tanks can be used to collect solids and to skim floating material from a layer operation. A floating baffle or other separator can be installed to remove egg shells, feathers, and other debris. The tank should be placed between the layer house and a waste storage pond or lagoon. Normally, a settling tank is 4 feet at the deep end, sloping to ground level. Walls are slotted to allow drainage of the settled waste.

It is recommended that two settling tanks be installed; one can be drained and cleaned while the other remains in operation. The tanks must be properly constructed and sealed to prevent groundwater or surface water pollution. In tanks and storage ponds, unpleasant odors and dangerous gases may be present and may require protective measures.



Figure 1.—Shallow-pit poultry house with cages.



Figure 2.—High-rise poultry house with cages.

Treatment Lagoons and Ponds

Semisolid or liquid manure can be removed from the pits (by flushing or scraping) and stored in below- or aboveground storage tanks, steel storage tanks, or holding ponds. Lagoons, a type of earthen storage basin, have a manure treatment function in addition to a storage function. Lagoons use anaerobic or aerobic bacteria to decompose the waste, and they can even be used as digesters to convert large masses of waste into gases, liquids, or sludge.

Lagoons are easy to manage, convenient, and cost-efficient. Storage and land application can be handled more opportunely if the grower has a lagoon, and labor costs and operating costs are slight after the initial investment. Such facilities became a somewhat popular component of waste management systems during the 1970s when the interest shifted from simply using waste for fertilizer in land applications to treating the waste to produce a more conven-

ient waste management system overall (with less organic content to land apply).

The decomposition process will be anaerobic or aerobic. Anaerobic bacteria in animal waste (i.e., bacteria that live in animal intestines) cannot work in the presence of oxygen. Aerobic bacteria, on the other hand, must have oxygen; therefore, anaerobic lagoons are deep and airless; aerobic lagoons are spread over a large surface area, take in oxygen from the air, and support algae. Both aerobic and anaerobic lagoons provide storage and disposal flexibility.

Other factors, however, must also be considered. Anaerobic lagoons are a source of odors and nitrogen losses and may require frequent sludge removal if they are undersized. Groundwater protection may be difficult to secure in either system. If mechanical aeration is used for an aerobic system, energy costs must be included in the accounting. Proper management is essential for lagoon maintenance and operation.

Aerobic Lagoons

The design, shape, size, capacity, location, and construction of the lagoon depends on its type. Aerobic lagoons require so much surface area (to maintain sufficient dissolved oxygen) that they are an impractical solution to most waste management problems. They may require 25 times more surface area and 10 times more volume than an anaerobic lagoon. Nevertheless, some growers may consider using an aerated lagoon — despite its expense — if they are operating in an area highly sensitive to odor.

Some of the sizing difficulty can be solved by using mechanical aeration — by pumping air into the lagoon — but the energy costs for continuous aeration can be high. Aerobic lagoons will have better odor control, and the bacterial digestion they provide will be more complete than the digestion in anaerobic lagoons.

Lagoon design and loading specifications should be carefully followed and monitored to increase the effectiveness of the treatment. No more than 44 pounds of biological oxygen demand (BOD) should be added to the lagoon per day per acre. The lagoon should have sufficient depth so that light will penetrate the 3 or 4 feet of water. Effluents from the lagoon should be land applied to avoid long-term ponding and to make economical use of the nutrients that remain in them.

Anaerobic Lagoons

Anaerobic treatment lagoons are earthen basins or ponds containing diluted manure that will be broken down or decomposed without free oxygen. In the process, the organic components or BOD in the manure will be liquified or degraded naturally.

Anaerobic lagoons must be properly designed, sized, and managed to be an acceptable animal waste treatment facility.

Liquid volume rather than area determines the size of anaerobic lagoons. The lagoon should accommodate the design treatment liquid capacity and the amount of wastewater to be treated; it should also have additional storage room for sludge buildup, temporary storage room for rain and wastewater inputs, extra surface storage for a 25-year, 24-hour storm event, and at least an additional foot of freeboard to prevent overflows.

The design criteria for anaerobic lagoons are based on the amount of volatile solids to be loaded each day. The range is from 2.8 to 7.0 pounds of volatile solids per day per 1,000 cubic feet of lagoon liquid. The amount of rain that would collect in a 24-hour storm so intense that its probability of happening is once in 25 years requires at least 5 to 9 inches of surface storage, although the actual volume of surface storage required is site specific.

To protect the groundwater supply, lagoons should not be situated on permeable soils that will not seal, on shallow soils, or over fractured rock. The bottom of the lagoon should not be below the water table. Nor should mortalities be disposed of in lagoons. In fact, screening the wastes before they enter the lagoon helps ensure complete digestion and the quality of the wastewaters for land applications. If the site's topography indicates a potential for groundwater contamination, then any earthen basin should be lined with clay, concrete, or a synthetic liner.

New lagoons should be filled one-half full with wastewater before waste loading begins. Planning start up in warm weather and seeding the bottom with sludge from another lagoon helps to establish the bacterial

population. Because bacterial activities increase in high temperatures, lagoons, in general, work best in warm climates. Manure should be added to anaerobic lagoons daily, and irrigation (drawdown) should begin when the liquid reaches normal wastewater maximum capacity. The liquid should not be pumped below the design level treatment, however, because the proper volume must be available for optimum bacterial digestion.

Drawdown (that is, the lagoon liquid) can be used for land applications guided by regular nutrient management planning and sampling of the lagoon liquids and soils to ensure safe and effective applications. When sludge accumulation diminishes the lagoon's treatment capacity, it, too, can be land applied under strictly monitored conditions.

Secondary lagoons are often needed for storage from the primary lagoon. Using a secondary lagoon for irrigation also bypasses some of the solids picked up in the primary lagoon. The size of secondary lagoons is not critical.

Information and technical assistance and some cost-share programs are available for producers who determine that a lagoon system should be part of their resource management system. The USDA Natural Resources Conservation Service (NRCS) and the Cooperative State Research, Extension, and Education Service offices can provide additional assistance.

Land Applications

Land application of liquid waste can be achieved with a manure slurry or irrigation system. If the application falls directly on the crop, care must be taken to prevent ammonium toxicity and burning. Because raw manure contains high amounts of uric acid, it should be thoroughly mixed before application. Layer lagoon sludge is more dense than a pullet lagoon sludge because of its high grit or limestone content and should be diluted before application.

Timing is a major factor in successful land applications. There should be no land application prior to, during, or immediately following a rainfall event. The manure must also be uniformly applied — whether you are using a manure spreader or an irrigation system. The operator should be particularly careful (especially during a drought) not to coat the plants with lagoon liquid. Instead, make several small applications of lagoon liquid, rather than one large one.

Liquid waste is primarily disposed of through land applications. Proper spreading on the land is an environmentally acceptable method of managing waste. However, with increasing environmental concerns and the need to match closely the fertilizer needs of crops, farmers can no longer afford to simply "spread manure."

The USDA NRCS, Cooperative State Research, Extension and Education Service, and other agencies offer poultry waste and nutrient management planning assistance. These offices have worksheets to help growers plan liquid waste management, which includes the following tasks:

- determining the amount and volume of waste generated;
- calculating land application requirements;
- sampling and analyzing the nutrient composition in poultry litter, manure, or slurry; and
- matching the nutrients available in these products with crop nutrient requirements for land applications.

Detailed information on how to prepare nutrient assessments, conduct soil testing, and calculate application rates, timing, and methods of application are also available from these agencies.

The use of nutrient management planning will help growers make economical and practical use of the organic resources generated on their farms.

References

Barker, J.C. 1990 rev. Lagoon Design and Management for Livestock Waste Treatment and Storage. Agri-Waste Management. EBAE-103-83. North Carolina Agricultural Extension Service. Agricultural and Technical State University of North Carolina, University Station.

Brodie, J.L., L.E. Carr, and C.F. Miller. 1990. Structures for Broiler Litter Manure Storage. Fact Sheet 416. Cooperative Extension Service, University of Maryland, College Park.

Fulhage, C. 1993. Land Application Considerations for Animal Wastes. WQ202. University Extension, University of Missouri, Columbia.

Merka, W.C., and S.A. Thompson. 1997. Deep Litter Composting as a Means for Retrofitting Lagoon Flush Systems. Abstract. Presentation at the 18th Annual Meeting of the Southern Poultry Science Society and the Southern Conference on Avian Disease. World Congress Center, Atlanta, GA.

Michigan Agriculture Commission. 1991. Generally Accepted Agricultural Practices for Manure Management and Utilization. Lansing, MI.

Payne, V.W.E., and J.O. Donald. 1991. Poultry Waste Management and Environmental Protection Manual. Circular ANR 580. Cooperative Extension Service, Auburn, University, Auburn, AL.

Ritter, W.F. No date. Poultry System Design and Management for Environmental Protection. University of Delaware, Newark.

U.S. Department of Agriculture. 1992. National Engineering Handbook 210, Part 651. *In* Agricultural Waste Management Field Handbook. Soil Conservation Service, Washington, DC.

U.S. Department of Agriculture. 1993. Agricultural Waste Management Handbook. Part 651. Soil Conservation Service, Washington, DC.

Watson, H. 1990. Liquid Manure Handling Systems. DTP 12/90-018. Alabama Cooperative Extension, Auburn University, Auburn, AL.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 4 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Composting Waste Products

Poultry litter or layer manure is most often land applied to pastures and crops for its value as an organic fertilizer. We know from long experience how beneficial this practice can be when soil and manure nutrient testing are integrated with crop nutrient needs to determine the amount and timing of the application. This integration makes it possible to approach land application as a wise use of resources rather than as a disposal method.

Proper storage and treatment of poultry by-products (litter, manure, hatchery waste, and dissolved air flotation [DAF] skimmings) before use are important to minimize compositional changes and decrease odor and handling problems. Depending on the by-product, dry storage, ensiling, or composting may be appropriate treatments. Resource management systems may include incineration and burial as methods of disposal; however, these techniques are not called treatments because they do not usually provide any reusable products.

Composting is an environmentally sound and productive way to treat poultry by-products and mortalities (see also PMM/4 and PMM/5). The product of composting is easier to handle, has a smaller volume, and is a more stable product than the raw materials. The nutrient content of the compost will be nearly the same as the starting materials if the composting is performed properly.

While compost can be land applied to decrease the need for nutrients from commercial fertilizers, composted by-products may also be marketed for higher value uses on turf, for horticultural plant production, and in home gardening landscaping. It can be added as an amendment to soils for transplanting flowers, trees, and shrubs, or to establish new lawns. Compared to commercial fertilizers, poultry by-product compost will have a lower nutrient analysis (e.g., 2-2-2) for nitrogen, phosphorus, and potassium. However, there are other benefits to the soil and plant growth associated with the organic matter and micronutrients in compost.

Understanding the Process and Benefits of Composting

Composting is a natural, aerobic, microbiological process in which carbon dioxide, water, and heat are released from organic wastes to produce a stable material. Leaves and other organic debris are subject to this process all the time — that is, the activity of microorganisms transforms these materials into a soil-like, humus-rich product.

This natural process can also be used as a resource management technique to transform large quantities of litter, manure, and other poultry by-products into compost. The conditions under which natural composting occurs can be stimulated and controlled so that the materials compost faster and the nutrient value of the compost is maximized.

The composting process is relatively simple:

1. By-products, for example, litter, manure, eggshells, hatchery waste, and DAF skimmings, are placed in bins, piles, or elongated piles called windrows. A bulking agent or carbon amendment (e.g., sawdust, wood chips, yard waste, or paper that is rich in carbon but low in other nutrients) is usually necessary to provide the proper ratio of carbon to nitrogen in the mix and to improve aeration.

2. Air is needed to support and enhance microbial activity. Because the composting microorganisms are aerobic, that is, oxygen using, the windrows and compost piles must be aerated to ensure the

efficiency of the process. Sufficient aeration also minimizes the formation of objectionable odors that form under anaerobic (oxygen depleted) conditions. Adequate aeration can be provided by forced air systems, such as blowers or fans; or by turning the compost with a front-end loader or a commercially available compost turner as required.

3. Mechanical agitation or turning of the materials supplies aeration, helps mix the materials, and distributes any added water.

4. Temperatures in the compost must be maintained at levels above approximately 130°F to kill any pathogens (disease-causing organisms) and promote efficient composting. Temperatures above 150 to 160°F should be avoided because they reduce the microorganisms that are beneficial to the composting process.

5. Adequate moisture, between 50 and 60 percent, is necessary for optimal microbial activity.

Handling Compost

Compost produced from poultry by-products can be used in many different ways: it can be used directly as a soil amendment for agricultural or horticultural uses; pelletized or granulated for ease of transportation and application; or enhanced with conventional fertilizers to improve its nutrient value.

Even though composting is a relatively new manure management technology, the off-farm market is clearly growing. Consumer awareness of the safety and convenience of the product is beginning to penetrate the market. Current limiting factors are growers' unfamiliarity with marketing strategies and competition from less costly products.

Possible Drawbacks

Composting, like any management technique, cannot be undertaken lightly, whatever its benefits. It requires a commitment of time and money for equipment, land, storage facilities, labor, and management. Composting is an inexact process that depends heavily on the quality and characteristics of the materials being composted and the attention given to the composting process.

Although the finished product should have no odor or pest problems, such problems may occur during the composting process. Weather may also affect the process adversely. Compost releases nutrients slowly — as little as 15 percent of the nitrogen in compost may be available during the first year of application. In addition, costs associated with production-scale composting can be significant, and federal and state regulations for stormwater runoff from the composting site must be followed.

Despite these potential drawbacks, composting on the farm is a practical resource management technique. Good management will consider every opportunity to eliminate or reduce the concerns associated with composting while maximizing its benefits. Once it is realized that composting can be more than a "dump it out back and forget it" procedure, the technique can be used and adjusted to meet by-product management needs.

Composting Methods

There are four general methods of composting: passive composting, windrows, aerated piles, and in-vessel composting.

▼ **Passive composting** is the simplest, lowest cost method. It requires little or no management because the materials to be composted are simply stacked into piles and left to decompose naturally over a long time.

Passive composting is not suitable for the large quantities of litter or manure produced on poultry farms. It occurs at comparatively low temperatures and decomposition occurs at a slow rate. Anaerobic conditions resulting from insufficient aeration can result in objectionable odors.

▼ **Windrow composting** occurs in long narrow piles that can vary in height and width depending on the materials and equipment available for turning.

For most efficient composting, windrows are turned as required depending on temperature and oxygen measurements.

Windrow composting (Fig. 1) is usually well suited to poultry farms. In this method, the windrows are formed from the material to be composted, water, and any bulking agent or carbon amendment. The piles can range from 3 feet high for dense materials to as high as 12 feet for lighter, more porous materials like leaves. If the piles are too large, anaerobic conditions can occur in the middle; if they are too small, insufficient heat will be maintained for pathogen reduction and optimum microbial activity.

The windrows are turned periodically to add oxygen, mix the materials, rebuild porosity (as the mixture settles), release excess heat, and expose all materials equally to the high interior heat that kills pathogens. Turning can be labor and equipment intensive depending on the method used. In the beginning, it may be necessary to turn daily or even several times a day to maintain sufficient oxygen levels; however, turning frequency declines with the windrow's age.

In addition to needing space for the windrows, the producer will also need turning equipment, a source of water, a dial thermometer, and perhaps an oxygen meter. The turning equipment (Fig. 2) can be front-end loaders, manure spreaders with flails and augers to provide good mixing, or specialty machines. Often older, unused farm equipment, for example, an old potato plow and a farm tractor, can be used for turning compost.

Temperatures within the windrow are most commonly used to determine when turning is necessary. Low temperatures and odors are signs that more oxygen is needed, while cool or hot spots at intervals along the windrow indicate that the material needs to be mixed. During fly season, all windrows should be turned at least weekly. In the winter, windrows can be combined to conserve heat as they diminish in height. Composting time can vary from weeks to months depending on the material being composted, the attention given to composting conditions, and the quantity of material composted.



Figure 1.—Typical windrow shapes and dimensions.



Figure 2.—Windrow composting with an elevating face windrow turner.



Figure 3.—Passively aerated windrow method for composting manure.

▼ **Aerated static composting eliminates the** labor of turning the compost by using perforated pipes to introduce air into piles or windrows.

Air can be supplied passively, or with blowers to force air into or through the composting material.

Passively aerated windrows (Fig. 3) are a modification of windrow composting that eliminates turning. In a commonly used system, the windrow is placed on a base of wood chips, straw, or peat, and perforated

aeration pipes are added on top of this base. The material to be composted must be very well mixed, since it is not turned, and the windrow should not be higher than 3 to 4 feet. This method has the advantage of minimizing odors and helping to conserve nitrogen.

Aerated static piles or windrows add blowers to the aeration pipes. This method allows larger piles or windrows and permits more efficient composting than passively aerated static piles. Air can either be drawn into or forced through the composting material. The blowers may be controlled to turn on at set intervals or in response to temperatures in the pile or windrow.

▼ **In-vessel composting** is similar to aerated methods but the materials to be composted are contained in bins or reactors that allow for control of aeration, temperature, and mixing, in some systems.

In-vessel composting is actually a combination of methods that involve both aeration and turning. The advantages of in-vessel composting include the elimination of weather problems and the containment of odors. In addition, mixing can be optimized, aeration enhanced, and temperature control improved.

The simplest form of in-vessel composting is bin composting, which is readily adaptable to poultry farms. Bins may be plain structures with wood slatted floors and a roof, conventional grain bins, or bulk storage buildings. Other types of in-vessel composters use silos in which the air goes in at the bottom and the exhaust is captured for odor control at the top; agitated bed systems; and rotating drums. Costs for equipment, operation, and maintenance for a large quantity of materials are high for in-vessel composting.

Factors to consider in choosing a composting method are speed, labor, and costs. Windrows are common on farms; they can use existing equipment, no electricity is required (so they can be remotely located), and they produce a more uniform product. They are, however, also labor intensive and at the mercy of the weather. Adding a paved or compacted clay surface and a simple open-sided building can minimize weather problems and the impact of composting on water quality.

For more information, technical assistance, and possible cost-share programs that may be available to help you begin a composting operation, contact your local conservation district office, the USDA Natural Resources Conservation Service, or the Cooperative State Research, Extension, and Education Service.

References

Biocycle. 1991. The Art and Science of Composting. The JG Press, Inc., Emmaus, PA.

Cabe Associates, Inc. 1991. Poultry Manure Storage and Process: Alternatives Evaluation. Final Report. Project Number 100-286. University of Delaware Research and Education Center, Georgetown.

Carr, L.E. 1997. Composting Poultry Litter. Congressional Animal Waste Conference. Longworth House Office Building, Washington, DC

Carr, L.E., R.C. Moore, and C.A. Johnson. 1992. Composting Dissolved Air Flotation Skimmings from Poultry Processing. ASAE Paper 92-6016. International Summer Meeting of the American Society of Agricultural Engineers. Charlotte, NC.

———. 1992. Hatchery Waste Composting. Proceeding of the 1992 National Poultry Waste Management Symposium. Sheraton Civic Center Hotel, Birmingham, AL. ISBN 0-9627682-6-3, pp. 139-144.

Donald, J.O., C.C. Mitchell, and C.H. Gilliam. 1990. Composting Agricultural Wastes in Alabama. ANR Circular 572. Cooperative Extension Service, Auburn University, Auburn, AL.

Rynk, R., editor. 1992. On-farm Composting Handbook. NRAES-54. Cooperative Extension. Northeast Regional Agricultural Engineering Service. Ithaca, NY.

Smith, B. 1993. Composting and Uses for Manure. Presentation. 1993 Waste Management and Water Quality Workshop. Southeastern Poultry and Egg Association, Atlanta, GA.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 5 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Putting Nutrient Management to Work

Land application, especially field spreading, is in most cases the best use of poultry wastes. It recovers nutrients that would otherwise be lost, improves yield, and reduces the possibility of releasing this material to water and the environment.

Where land is available, manure applications can be substituted for commercial fertilizers, reducing the farmers' costs and helping them comply with environmental laws. At the same time, land applications tend to use the largest amount of waste closest to the point of production.

To ensure that nutrients in waste are not overapplied to the land, the waste must be analyzed for the amount and type of nutrients it contains and the timing of applications must be adjusted to ensure that growing plants can use the nutrients. To accomplish this outcome, the litter should be uniformly applied at the recommended rate. The management practice that offers this assurance is nutrient management planning.

Nutrient management planning as a preliminary to land application has become a standard practice for recovering and using the nutrients in solid and liquid animal waste. It is, like composting, a centuries-old practice, which modern technology has substantially improved. The improvement — in a word — the ability to plan exactly how much manure should be applied — was highly recommended in the early 1990s. In 1995, the poultry industry in the Commonwealth of Virginia announced the decision of its four major integrators to require all new producers to have nutrient management plans. Nutrient planning has since become a requirement in many states.

What Is a Nutrient Management Plan?

Nutrient management planning matches the nutrient needs of the plants and soil with the nutrient contents in the manure to achieve a proper nutrient balance. An effective nutrient management plan consists of the following core components:

- farm and field maps,
- realistic yield expectations for the crops to be grown,
- a summary of the nutrient resources available (the results of soil tests and nutrient analyses of manure, sludge, or compost),
- an evaluation of field limitations based on environmental hazards or concerns (e.g., sinkholes, land near surface water, highly erodible soils, steep slopes),
- application plans based on the limiting nutrient,
- plans that include proper timing and application methods (avoid application to frozen soil and during periods of leaching or runoff), and
- calibration of nutrient application equipment.

Experience will continue to refine this practice. For example, nutrient management is very often based on nitrogen as the limiting nutrient. Nitrogen is a challenging nutrient to manage; it is highly mobile, easily dissolving in runoff and leaching through soil. Phosphorus, on the other hand, is less mobile so it is less likely to move off-site. Buffer zones and filter strips are also planted at the edge of fields and around water

resources — to protect them from both nitrogen and phosphorus.

Now, however, soil tests and soil performance are showing relatively high phosphorus levels even in areas that have not been traditionally high in phosphorus. In some cases, these levels are so high that phosphorus must now be used as the limiting nutrient; in other cases, the levels are so excessive that no phosphorus should be applied, perhaps for a very long time. And while buffer strips are helpful, they are not sufficient to reduce phosphorus to acceptable levels.

These conditions notwithstanding, phosphorus is an essential element in bird nutrition. Are we then facing a dilemma? If we go carefully into these new areas, probably not. The solution may be found in enzyme treatments or food additives. Many growers have shown that putting the enzyme phytase in the diet can help maintain bird health and reduce the amount of phosphorus in litter. Phosphorus reductions can also be achieved by treating litter and field soils with alum. As alum treatments also reduce ammonia volatilization, growers are once again provided with a key management notion: good waste management, bird nutrition, and maintaining good management practices year-round are interrelated.

The USDA Natural Resources Conservation Service and Cooperative State Research, Extension, and Education Service offices have prepared tables of the mean average amounts of key nutrients found in different kinds of manure (Table 1). These tables may be used to estimate the nutrient content of your waste source or stockpile. However, as this resource is produced and used under many different circumstances, it is always best to have samples of your supply tested periodically by a certified state or private lab.

Preparing Samples

Always prepare your samples from six to 12 representative areas in the poultry house or from at least six different locations in the stockpile. (Samples collected from the stockpile should be taken from a depth of about 18 inches; careful handling will ensure that no soil is intermixed in the sample.) Samples should be taken as close as possible to the time of application; however, allow sufficient time to receive test results.

To collect the sample, obtain a quart of waste from six to 12 locations in the house or stock pile and place them in a large, clean bucket. Mix the contents thoroughly; then place about a quart of the mixed sample into a clean plastic bag or bottle. Seal it tightly, but allow room for the sample to expand. Keep the sample cool; if it is not mailed to the laboratory on the same day as it was withdrawn from the source, then the entire sample should be refrigerated. The accuracy of the lab test depends on the quality of the samples collected. Contact the lab that will be analyzing your sample for information on collection, handling, and shipping.

For Best Results

Both dry and wet samples should be routinely tested on an "as is" basis for total nitrogen, ammonia-nitrogen, phosphorus, and potassium. The key to successful land applications is to apply the right amount of nutrients at the right time, using the right method so that the waste's nutrient content is closely correlated with the nutrient needs of the plants and soil. Be aware that some nutrients will accumulate in the soil and reach high levels; apply the product immediately before planting, during a high growth season, and not in bad weather (when the nutrients may be washed away). Incorporate waste into the soil, if possible. For best results, use biennial soil tests in connection with your manure sample and basic calculations.

Land Application Rates and Methods

Whether the poultry manure or litter waste is taken to nearby farms or spread on your own land, the amount applied, the timing of the applications, and the methods used will affect the outcome. Understanding how the soil and manure or litter interact and calibrating the spreader will help growers apply the right amount at the right time in just the right way.

Manure spread on the surface and not worked into the soil will lose most of its volatile nitrogen compounds, which will be released as ammonia gas to the atmosphere. This release may or may not represent a pollution potential, but such lost nutrients are not available for plant growth.

Poultry waste spread on frozen or snow-covered soil has a high potential for runoff to

Table 1.—Average Nutrient Composition of Poultry Litter, measured in lbs/ton on an as is basis.

	N	NH_4^+–N	P_2O_5	K_2O	Ca	Mg	S	Na	Fe	Mn	B	Mo	Zn	Cu
Broilers														
Stockpiled litter	36	8	80	34	54	8.0	12.0	6.2	1.5	0.59	0.041	.00069	0.55	0.27
Layers														
Undercage	28	14	31	20	43	6.1	7.1	4.5	0.52	0.27	0.050	.00390	0.32	0.036
Highrise stored	38	18	56	30	86	6.8	8.8	5.0	1.8	0.52	0.046	.00038	0.37	0.043
Turkey Litter														
Stockpiled	36	8	72	33	42	6.8	9.5	6.4	1.5	0.62	0.047	.00095	0.56	0.34
Duck Litter														
Stockpiled	24	5	42	22	27	4.4	5.6	8.8	1.2	0.47	0.030	.00030	0.47	0.50
Liquid Layer														
Liquid slurry	62	42	59	37	35	6.8	8.2	5.3	2.9	0.42	0.040	.018	0.43	0.080
Lagoon sludge	26	8	92	13	71	7.2	12.0	4.2	2.2	2.3	0.082	.014	0.80	0.14
Lagoon liquid	179	154	46	25	266	7.4	52.0	51.0	2.0	0.24	0.37	.020	0.70	0.19

Source: Adapted from Soil Facts: Poultry Manure as a Fertilizer Source (Zublena, Barker, and Carter, 1993).

Key: N = nitrogen
NH_4^+–N = ammonium
P_2O_5 = phosphorus
K_2O = potassium
Ca = calcium
Mg = magnesium
S = sulfur
Na = sodium
Fe = iron
Mn = manganese
B = boron
Mo = molybdenum
Zn = zinc
Cu = copper

surface water. It should not be surface applied to soils near wells, springs, or sinkholes or on slopes adjacent to streams, rivers, or lakes. In fact, some states prohibit this activity. Conservation practices can reduce runoff, nutrient loss, and pollution.

Water pollution potential can be decreased, and the amount of waste nutrients available to plants can be increased, by working poultry waste into the soil either by tillage or by subsurface injection. Subsurface injection of waste only minimally disturbs the soil surface and would be appropriate for reduced till and no-till cropping systems.

Manure or litter must have time to break down before the nutrients in it become available to the crop. Fall applications allow this breakdown to occur, but some of the nitrogen in the manure may be lost through leaching and runoff. Spring applications prevent this nitrogen loss but do not allow enough time for the breakdown of the manure. Incorporation of poultry waste beneath the soil surface in the fall is a way to conserve the nutrients and protect water quality.

Spring and summer applications are recommended based on plant uptake, though it is always important to check for good weather before applications are planned. If litter is applied in bad weather, nutrients may be lost in stormwater runoff. Nutrient-enriched runoff from agriculture could be a leading cause of nonpoint source pollution.

How the poultry waste is applied also affects how quickly the nutrients are incorporated. Generally, incorporation within 12 hours is ideal. The waste can be broadcast over the whole field, followed by incorporation tillage. This method has the advantage of good distribution; because it is visible, the grower can determine the uniformity of the broadcasting. There will, of course, be some odor on the day of the application. Farmers may also want to investigate incorporation, topdress, sidedress, and band application methods.

Spreader Calibrations

Calibration of the spreader machine is also necessary to monitor and control the amount and uniformity of the application. Calibration specifies the combination of settings and travel speed needed to apply nutrients at a desired rate. By knowing a spreader's application rate, and using a few basic calculations found in various fact sheets, a producer can correctly apply the nutrients to meet the needs of the

plants. Generally, there are two types of nutrient spreaders — solid or semisolid and liquid. Broiler growers handle solid or semisolid nutrients; many egg producers have liquid waste systems.

Solid or semisolid waste is usually handled in box-type or open-tank spreaders, and the application rate is expressed in tons per acre. Nutrient concentrations in pounds per ton can be estimated, or calculated from the lab analysis. The nutrient application rate in pounds per acre must be determined, based on the tons per acre of waste application.

Liquid or slurry waste is usually handled by tank wagons or irrigation systems, and the application rate is expressed in gallons per acre. Nutrient concentrations in pounds per gallon (or pounds per 1,000 gallons) can be estimated or obtained from lab analysis and used with the application rate in gallons per acre to obtain pounds per acre nutrient applied.

The volumetric capacity of spreaders is generally provided by the manufacturer. Caution should be exercised in using manufacturer's data for spreader volume. A more accurate and preferred approach is to calibrate your own equipment.

Assistance is available from the USDA Natural Resources Conservation Service or Cooperative State Research, Extension, and Education Service offices to calibrate your spreader. Worksheets are available to determine spreader capacity and application rate. Unless the waste has been analyzed for nutrient content and unless the crop soil nutrient needs are known, spreader calibration may have little effect on the application's success.

Once the desired application rate is obtained, record the pertinent information so that you do not have to recalibrate the spreader each time it is used. Spread poultry wastes in a uniform manner. If lush, green growth and not-so-lush growth of plants are observed, adjustments will need to be made during the next application. Calibration of the nutrient spreader is an important practice that is economically and environmentally useful.

A nutrient management plan should be periodically updated to ensure its effectiveness. Often nutrient management can save a producer money by reducing the amount of fertilizer purchased. This reduction in cost is a result of accounting for nutrients already in the soil and manure. For more information, or for nutrient management planning assistance, contact your local USDA Natural Resources Conservation Service or Cooperative Extension Service office or a nutrient management consultant in your area.

References

Barker, J.C. 1990. Livestock Waste Sampling, Analysis, and Calculation of Land Application Rates. Reprint. EBAE 111-84. Agricultural Extension Service, North Carolina State University, Raleigh.

Brodie, H.L., and V.A. Bandel. 1990. Manure Testing. FS-430. Cooperative Extension Service, University of Maryland, College Park.

Fulhage, C.D. 1989. Reduce Environmental Problems with Proper Land Application of Animal Wastes. WQ201. University Extension, University of Missouri, Columbia.

———. 1992. Land Application Considerations for Animal Wastes. WQ202 University Extension, University of Missouri, Columbia.

Goan, H.C., and J. Jared. 1991. Poultry Manure: Proper Handling and Application to Protect Our Water Resources. PB1321. Cooperative Extension Service. North Carolina State University, Raleigh.

Ogburn, C.B., and J.O. Donald. 1990. Calibrating Spreaders for the Application of Animal and Poultry Manure. DPT Circular 11/90-006. Cooperative Extension Service. Auburn University, Auburn, AL.

Woodward, M. No date. Manure Spreader Calibration Work Sheet. Technical Note 4. Cooperative Extension Service, Pennsylvania State University, Lancaster.

Zublena, J.P., J.C. Barker, and T.A. Carter. 1993. Soil Facts: Poultry Manure as a Fertilizer Source. AG-439-5. North Carolina Cooperative Extension Service, Raleigh.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 6 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Economics of Transporting Poultry Manure and Litter

Managing large amounts of poultry litter successfully can involve economic and environmental issues that intertwine and often appear nearly insurmountable. For example, when land suitable for spreading poultry litter as a fertilizer is not available or not under the control of the poultry grower, new markets for land applications and new ways to use the waste must be found. For some years, high quality poultry waste has been marketed both as a fertilizer and as beef cattle feed. Marketing this material involves transportation from the point of production to the point of use.

A Concentrated Industry

The locations of most poultry growers are concentrated within a 25 to 50 mile radius of a hatchery, feed mill, or live-bird processing plant. When the production radius increases over 25 miles, the cost of broiler production increases one cent per pound. This increase, resulting from a combination of labor and transportation, can cost a broiler production unit an additional $2 million annually.

The cost of protecting and preserving water quality must also be applied. Is it better to increase the area of production so that all waste products can be accommodated? Or better to transport the by-products to other areas?

For example, suppose that a broiler complex, which includes pullets and breeders, handles about one million birds a week. These birds will produce about 65,000 tons of litter annually. At the rate of 4 tons per acre, the producer will need 16,250 acres to use the litter for land applications. If more than the one company is operating in the area, even more waste will be produced and more land will be needed.

One alternative to land applications in the area of production is to generate markets or disposal areas at a point some distance from the point of production. Growers will need to find buyers for their poultry waste, and develop a transportation system or delivery network. In some instances, custom cleanout operators will broker and transport the litter for a percent of the profit.

Estimating the Break-even Point

Because of the bulkiness of the solid or semi-solid product, transportation will be the litter buyer's highest cost. An average farm truck can carry 9 to 12 tons. A 30-foot, open trailer used for transporting grains can carry 18 to 24 tons. As load size increases, the cost per ton should decrease.

Figure the cost on a round-trip basis, but if you can schedule back-hauls in the empty truck, you can push the cost even lower. Early estimates predict the cost of transporting litter to be about $1 per mile on a round-trip basis for a 20-ton load. Back-hauls are certainly feasible, with proper attention given to handling, maintenance, and truck cleaning to prevent the spread of pathogenic bacteria and viruses. At least one integrator (Tyson Foods) has approved the use of the same trucks for delivering clean bedding and back-hauling litter.

If the grower is paid a per ton price ranging from $5 to $10, and the litter has a value of $22 to $28 as a fertilizer or $40 to $80 as a feed ingredient; the buyer can afford to transport the litter 100 miles for land applications or up to 300 miles for use as a feed. These distances can be increased if sufficient litter applications are made in the buyers' watersheds to convince farmers that spreading litter on their farms re-

ally does improve soil quality and increase crop yields.

The key to this outcome depends on the poultry growers designing and operating animal waste management systems that increase the quality and uniformity of the litter. When both sides are thus engaged, the price of the litter will reflect a fair exchange between what the growers and transporters are paid and the value of the product to the buyers.

Other Practical Considerations

A method is needed for loading raw litter into trucks that have 11-foot sides. Front-end loaders or an elevator that can be loaded with a smaller tractor or skid loader will work. The storage facility must have a smooth hard pad to accommodate the loading process, and the litter must be free of foreign materials such as soil, rocks, broken glass, or other debris. It should also be covered during storage and transportation to prevent losses, protect it from stormwater runoff, and prevent any negative perception of the poultry industry by the public.

Roads and turn-around areas at both ends of the trip must be large enough to accommodate the trucks and the loading and unloading process, and storage facilities must exist at the delivery depot if land applications or other use will be delayed.

The quality of the waste must be protected, and its transport must be biologically secure. Poultry waste should be transported only from well-managed and disease-free farms. All trucks should be properly cleaned and disinfected, and any leakage from the trucks should be drained and diverted from runoff and groundwater. Before being transported off-farm, the product should be deep stacked so that the heat in the stack can kill any harmful microorganisms. The heat level must be monitored to avoid reducing its nitrogen content or creating a fire hazard. Growers may also develop composting or pelletizing treatments to reduce the litter's bulk and odor.

Developing a Transportation Network

The knowledge that litter can be safely and economically transported is not likely to increase its use immediately. In fact, regulations often discourage or prohibit spreading the litter anywhere but on the growers' own crops; and many farmers who have croplands available are convinced that other problems associated with litter, such as handling problems, high transportation costs, and environmental risk, undercut its usefulness. In addition, other waste generators are competing for the same land and can often supply their product at lower cost.

Changing conventional attitudes and helping busy, often undercapitalized farmers develop environmental and market savvy is a long-term objective that requires cooperation among all players: farmers, their research and industry partners, government decisionmakers, environmentalists, and the public.

An example of such cooperation is Winrock International Institute's three-year effort to create a market for poultry litter in Arkansas (see box). Winrock's effort was supported by the USDA Sustainable Agriculture Research and Education program, had many government and private partners, and no doubt, stands among other similarly innovative projects in other regions and countries. It is unique, however, in its determination to use the emerging market for poultry litter to "link and resolve two environmental issues": poor soil quality in some agricultural watersheds and an oversupply of poultry wastes in others.

The Winrock initiative led to progress in rural productivity, sustainability, and equity. It also involved major obstacles:

- farmers are not marketers by training or inclination, and most people living on the margin are risk adverse;
- information and training are difficult to disseminate;
- management practices must be implemented to increase the nitrogen content of litter and its overall quality;
- certification and training are needed for clean-out contractors; and
- emerging markets for litter, like other new product marketing, may need to be subsidized.

More important, perhaps, than any other consideration: the cost of transporting litter long distances and the transportation infra-

structure generally must be carefully managed to ensure that the litter being moved is actually moving away from production areas with the most critical environmental stresses.

Ground-testing the Possibilities

Currently, a broker in central Arkansas is shipping about four 24-ton trucks of litter per day to row-crop farmers in the Arkansas delta, Mississippi, and Missouri. The cost to the buyer is $28.50 per ton for litter delivered a distance of several hundred miles.

Most of the transported litter is currently used as a soil builder and yield booster, though high quality, odor-free compost is also being marketed for use on golf courses, and in other specialty markets. These long-haul brokerage services began as enterprising local clean-out businesses. While subsidies are still needed to strengthen the market, the development and acceptance of high quality litter as cattle feed (a higher priced product) could ensure the truckers' long-term future.

At this stage, truckers depend on the research and information campaigns sponsored by federal and local agencies, agricultural foundations, and independent researchers, but the emerging market is also a catalyst for new research and farming opportunities. Indeed, the relationship between animal waste management technologies and a thriving litter transportation market is symbiotic. Both are needed to

- provide additional income to poultry growers,
- depend on incentives rather than regulations to encourage proper waste management practices,
- create a steady demand for litter in less developed watersheds, and
- create new job opportunities as well as cleaner water supplies in rural areas.

When one is convinced that litter is not a waste, but an economic asset, the logical next steps are to demonstrate its value and put it on the market.

Poultry Litter Goes to Market — Winrock's New Approach to Environmental and Rural Development

Rice farmers in western Arkansas often level their fields. The practice makes the fields easier to irrigate and drain and more accessible during bad weather. The grading, however, which is quite labor intensive, also leads to poor yields because it removes so much topsoil. The topsoil can be stockpiled during the grading and respread over the cut red clay; still, it can take some time before the fields return to high yields.

So when university researchers and some farmers began getting high yields using litter on graded soils, word of their success quickly spread to other farms. Soon cotton and soybean farmers were also using poultry litter on fields.

The loss of topsoil on leveled rice fields and other cropping practices are a potential threat to water and soil quality; so is the increasing volume of poultry litter in some regions. Using a well-planned waste management system to ensure that the litter is of high quality, then hauling it out of the threatened regions for application on croplands in other areas will solve both problems. The usefulness of the litter to crop farmers will raise growers' income even as the litter-improved soils lead to higher incomes for the farmers.

Winrock International disseminated the research findings, surveyed farmers and cleanout contractors to identify barriers to moving the litter, then linked the buyers and sellers, researchers and government resources, to begin the long process of creating a multistate market for poultry litter.

In this scenario, market forces replace regulations as a solution for environmental problems. As demand for the litter grows, so will production practices that enhance its quality and lead to new uses. The raw material can be processed for sale as potting soil, topsoil, fertilizer, plant food, and cattle feed ingredient. Moreover, as these products prove successful, other opportunities and products will be developed to increase litter's marketability and value.

The Farm Bureau has continued the project by managing the Poultry Litter Hotline. Call 1-800-467-3898 to buy or sell litter in Arkansas.

References

Donald, J.O., and J.P. Blake. 1990. Economics of Transporting Poultry Litter as a Fertilizer. DTP Circular 10/90-007. Alabama Cooperative Extension Service, Auburn University, Auburn, AL.

J. Harsch. 1995. Poultry Litter Marketing and Utilization Project: A Case Study 1992-1995. Winrock International, Morrillton, AR.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 7 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Feeding Litter to Beef Cattle

Cattle, so far as growth and performance can indicate, enjoy a basic diet of corn and soybean meal (for protein) and hay (for long, crude fiber). Broiler and turkey litter and caged layer waste (the latter has no litter content and is often called dried poultry waste [DPW]) can be mixed with the corn/soybean meal and fed to cattle and other ruminants (e.g., sheep and goats). This cost-effective mixture has been a common practice in the beef cattle industry for many years with no adverse effects on the animals' growth or the quality of meat and other food products processed from them for human consumption.

Indeed, as litter is a source of protein, energy, and minerals, its use as a feed ingredient helps conserve nutrients and offset other production costs. Nutrients in the litter (especially, nitrogen, phosphorus, and potassium) and various minerals are recycled to the land when excreted in the ruminants' manure. Therefore, even if the litter must be transported long distances, feeding it to ruminants can be an economical and environmentally sound waste management technique.

Although no problem arises as a result of feeding litter to cattle, the public perception of litter as a cattle feed is often based on misinformation. We readily accept and even prefer vegetables that are organically grown — mushrooms, for example, go directly from the manure bed to the grocery store — but we have a hard time accepting litter as a food ingredient. In reality, beef cattle and other ruminants have a unique digestive system — a four-chambered stomach — that is well able to process wastes and other by-products. A cow's food is broken down and processed much more completely than a plant assimilates food into its tissues.

Regulations on Feeding Litter

In 1967, the Food and Drug Administration (FDA) discouraged the use of litter as a cattle feed. But in 1980, FDA issued a statement leaving it to the states to oversee this practice. At least 22 states have current regulations. No state regulates the private use or exchange of litter for this purpose; many states, however, regulate this commodity on the commercial market.

Many states require that processed broiler litter offered for sale carry warning labels about the presence of any drugs that may be present in the litter. To minimize the potential for drug residues in the cattle, all litter feeding should be discontinued at least 15 days before the animals are marketed for slaughter. This responsibility for selling only wholesome animals falls on the producers, regardless of regulations.

Generally, carefully applied safety precautions — pretreatment (e.g., deep stack) to ensure pathogen control, a 15 day withdrawal period before slaughter, not feeding litter to lactating dairy cows, and not feeding litter with high copper concentrations to copper-sensitive sheep — are sufficient to address health concerns. Litter has in fact been used as a feed ingredient for 35 years without any reported adverse effects on human or animal health.

Nutritional Value of Litter

The kind and amount of bedding material used in a broiler house and the number of batches housed on the litter affect the nutritional value of the litter, which should always be tested before being used as a food product for ruminants. The average nutrient contents are as follows:

- **Moisture.** The moisture content of the manure has little nutritional value; but litter that is too dry may be unpalatable, and

litter that is too wet may be difficult to handle as a food ingredient. A moisture content in the range of 12 to 25 percent is acceptable.

▼ **Total Digestible Nutrients.** The sum of crude protein and crude fiber values is used to calculate the total digestible nutrients (TDN) in litter. If the litter has a calculated value of 50 percent TDN, it is comparable to hay as an energy source.

▼ **Crude Protein.** The average amount of crude protein in broiler litter is about 24.9 percent. But about 40 percent of that amount is probably nonprotein nitrogen or uric acid. Young cattle cannot use this nonprotein nitrogen as easily as mature cattle can, so broiler litter should only be fed to cattle weighing over 450 pounds.

▼ **Bound Nitrogen.** Insoluble or bound nitrogen occurs in litter that has been overheated. Bound nitrogen is less easily digested than other nitrogen. Average litter samples have 15 percent bound nitrogen; overheated litter may have as much as 50 percent bound nitrogen.

▼ **Crude Fiber.** The fiber source in litter comes mainly from the bedding materials. Ruminants, however, need long roughage, such as hay. At least 5 percent of the litter ration should be in the form of hay or other long roughage.

▼ **Minerals.** Excessive minerals in litter are not usually a problem, though excessive calcium can cause milk fever in beef cows at calving. Withdrawing the litter from the cows' food for 30 days overcomes this difficulty. Microminerals, such as copper, iron, and magnesium, are also present in large amounts. Copper should not be fed at more than 150 parts per million. It builds up in the liver but is usually not harmful.

▼ **Ash.** Ash content is an indication of litter quality and should not exceed 28 percent. For dirt floor houses, about 12 percent of the ash is made up of calcium, phosphorus, potassium, and trace minerals; the rest is soil. Management techniques that reduce the soil content in the litter should be practiced.

Survey of Broiler Litter Composition

In sum, all litter to be used as a beef ration should be analyzed — tested for nutrient content. Litter used for feed should have at least 18 percent crude protein and less than 28 percent ash. Litter that has too much ash is not suitable as a food ingredient. Not more than 25 percent of the crude protein should be bound or insoluble. If broilers are reared on dirt floors, the litter may be contaminated with soil during cleanout.

The number of broods reared on the litter prior to cleanout of the broiler house also affects the quality of the litter; the more broods reared (five or more), the higher the litter is in nutrients.

Charred litter, that is, litter that has been exposed to too much heat during storage and has a burnt wood appearance, is only half as digestible as litter stored in stacks that were protected from excessive heat.

Processing and Storing Broiler Litter

All litter, regardless of its source, should be processed to eliminate pathogenic organisms such as salmonella; pesticide residues; medicated poultry rations such as antibiotics, coccidiostats, copper, and arsenic.

Dead birds may not be composted with poultry litter if the litter is to be used as a feed ingredient.

Litter can be processed by fermentation (ensiled with other feed ingredients such as corn or sorghum), directly acidified, or heat treated. The easiest, most economical method of treatment is deep stacking. Deep stacking should be done for 20 days or more at a temperature of 130°F. Most of the antibiotics approved for chickens are also approved for cows, and deep stacking inhibits molds (mycotoxins). If stack temperatures exceed 140°F, the deep stack should be covered with a polyethylene tarp to exclude oxygen and avoid overheating. Covered litter stacks will reach a temperature high enough to destroy pathogens but not so high that nitrogen digestibility is threatened.

Suggested Rations

Table 1 indicates rations that can be fed to dry brood cows, lactating cows, and stockers. These rations are recommended guidelines, not abso-

Table 1.—Suggested Rations.

RATION NUMBER	1 DRY BROOD COW	2 LACTATING COW	3 STOCKERS
Ingredients	Pounds		
Broiler Litter	800	650	500
Cracked Corn	200	350	500
Total Pounds	1,000	1,000	1,000

lutes, since the nutrient levels in litter are variable. Vitamin A should be added to all rations. Supplementing winter and summer grazing for stocker cattle increases the animals' weight gain and the total beef produced. To reduce bloating, feed the animals Botavec or Rumensin.

Summary

Because ruminant animals can digest forages, other fibrous materials, and inorganic nitrogen such as urea, the use of litter and DPW as a low-cost alternative feed source for these animals is gaining worldwide attention and acceptance. The use of broiler litter will become more widespread as the need for economy and responsible waste management becomes more urgent.

As animal production continues to increase and to concentrate geographically, more waste is produced than can be assimilated by land applications. However, when the litter is properly processed and stored, it can be used as a dietary supplement for cattle resulting in a lower winter feed cost for cattle and a cost-effective way to increase the average daily weight gain of cattle during the stocker production phase — the phase that begins after weaning and continues until the cattle are placed in the feedlot. This alternative to land application helps reduce the environmental risks and adds value to the litter. Since management practices on the farm affect the litter's quality, attempts to market the litter as a feed ingredient begin with a focus on management techniques.

References

McCaskey, T.A., A.H. Stephenson, and B.G. Ruffin. 1990. Factors that Influence the Marketability and Use of Broiler litter as an Alternative Feed Ingredient. Pages 197-203 *in* Proceedings of the Sixth International Symposium on Agricultural and Food Processing Wastes. American Society of Agriculture Engineers, Chicago, IL.

Ruffin, B.G., and T.A. McCaskey. 1990. Feeding Broiler Litter to Beef Cattle. Circular ANR-557. Cooperative Extension Service, Auburn University, Auburn, AL.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 8 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Horticultural Uses of Litter

Because it has essentially no unpleasant odors, well-composted broiler litter can be used indoors in a soilless potting medium. In fact, its nutrient content makes litter an ideal fertilizer for both indoor and outdoor gardens. It is also a good organic material for improving soil structure and drainage.

Soil Amendment

Gardeners can add composted litter to soils that otherwise contain too much sand or clay to support a garden. Work the top soil loose to a depth of 1 foot; then, spread 3 or 4 inches of compost on the soil. About 2 inches of compost may suffice at a minimum, but in really poor soils, 6 inches can be applied. Turn the soil over after the application to incorporate the compost.

Flower and Vegetable Transplants

Annual and perennial flowers and vegetable transplants also do well in compost-amended settings. Use a trowel to dig a hole in the new location. Remove the plant from its container and tear a hole in the bottom of the root-ball — otherwise, the roots will continue to grow in a tight circle — before setting it into the ground. Fill the hole with amended soil and water thoroughly. Mulching will help the plants retain water, thereby conserving this resource as well.

Transplanting Trees and Shrubs

If you are transplanting trees or shrubs, use the techniques listed above, but make sure that the hole you dig for the plant is at least twice the size of its present container. Work about 3 to 6 inches of composted litter into the soil in the hole and place the tree or shrub therein. Keep as much soil as possible around the root-ball when you take it out of the container. Do, by all means, remove the container, especially if it is plastic, so that the new growth will have plenty of room. The soil line on your plant should be level with your garden. Fill in the hole with the amended soil, and water the plant thoroughly to remove any air pockets that may have been in the backfill.

Potting Mix for Indoor Plants

To make your own potting medium, use equal parts of composted litter and composted pine bark — all living things need nitrogen and carbon. The bark may be screened to remove large pieces (one-half inch or larger) before mixing. Fill the new pot with 1 or 2 inches of the planting medium, spread out the roots of your plant, and set it in the pot. Remove any buds or flowers before replanting to ensure that the plant has time to get properly established. Transplant from one pot size to the next one only; skip one size if you have to, but don't go from a 1-inch pot to a 4-inch pot and expect to succeed. Water the plants in the fall and winter; fertilize them in the growing seasons — spring and summer.

Lawns

Composted broiler litter is a superior product to use to establish new lawn areas. Spread about 2 inches of composted litter on the area to be seeded. Then turn the soil over to a depth of 6 inches to incorporate the material. Place turf on the prepared soil and water it as usual. The addition of compost to the soil helps hold moisture and improves drainage.

Fertilizer

The nutritional analysis of composted litter will vary, depending on conditions of waste production and handling, among other variables. However, most composted litter will have an analysis similar to 2-2-2 commercial fertilizer. That is, it should have no less than 2 percent nitrogen (N), 2 percent phosphorus acid (P_2O_5),

and no less than 2 percent potassium as potash (K_2O). Two quarts of broiler litter compost can be applied monthly to your vegetable and flowering plants. It should be worked into the soil lightly — at the drip line or where the water falls naturally from the leaves.

References

Behe, B.K. 1990. Horticultural Uses of Composted Broiler Litter. Poultry By-product Management, Horticulture. DTP Circular 11/90-012. Cooperative Extension Service, Auburn University, Auburn, AL.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PWM / 9 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Controlling The Effects of Ammonia and Phosphorus

The effects of ammonia volatilization from litter can be significant at levels above 25 parts per million. It may adversely affect the birds' growth rate, feed efficiency, and egg production; damages the respiratory track; and increases the birds' susceptibility to a variety of avian diseases, including Newcastle disease, airsaculitis, *Mycoplasma gallisepticum*, and keratoconjunctivitis.

Ammonia volatilization from litter also contributes to acid rain. In Europe livestock wastes are considered the dominant source of ammonia pollution in acid rain, and emissions increased as much as 50 percent in the three decades leading to 1980.

Methods to reduce ammonia volatilization from litter usually require good housekeeping, proper ventilation, and perhaps chemical additives. Remediation can be costly but prevention is cost-effective and beneficial to farm workers, poultry, and the environment.

Ammonia emissions from litter during broiler production adversely affect bird health, increase ventilation costs, and cause significant ammonia emissions to the air. Improving nitrogen efficiency by feeding the flock amino acid diets can reduce the content of nitrogen in excrement and help control ammonia emissions.

Ventilating the poultry house before you have a problem; for example, when the house is new, the birds are young, and after cleanouts, is essential. Unless the house is properly ventilated at these times, ammonia problems may be just around the corner. Ventilating to prevent the problem will save growers increased heating and ventilation costs later in the growout.

Another tip: don't let your nose be your sensor. After several years in the poultry business, you may tolerate a higher level of ammonia in the air than is good for you or your operation. First time growers may be sensitive to ammonia at 10 parts per million; seasoned growers may be unaware of levels as high as 60 ppm. Operating costs, especially for fuel, will be lower at these levels, but so will the birds' performance.

Controlling house humidity will help you manage the ammonia and prevent litter from caking; it will also help control carbon dioxide, dust, and oxygen levels. Humidity in the house should be kept (ideally) at 50 to 70 percent.

Diluting the moist air inside the house with fresh outside air is the key to humidity control, so watch the weather. Warm, humid days will obviously increase the need for ventilation. Because it can be so difficult to gauge how much fresh air is needed, Georgia's Cooperative Extension Service has developed a list of timer settings and number of fans needed to maintain the average humidity in a 40 by 500-foot house during the six or eight weeks of growout (see Tables 1 and 2). You will want to check the weather conditions and perhaps consult with the Cooperative Extension office nearest your facility before adopting these tables.

Two other tips: First, if you are using the tables, consider the timer settings as minimum suggestions when the birds are young. The settings may be adjusted down slightly during extremely cold weather when the birds are older. To help you determine how much leeway you have, an inexpensive relative humidity and temperature gauge will be as useful as more expensive ammonia meters. The difference in

Table 1.—Small Birds (30,000).

BIRD AGE (weeks)	SECONDS ON (5-minute timer)	NUMBER OF 36" FANS
1	30	2
2	60	2
3	90	3
4	120	3
5	150	4
6	180	4

Table 2.—Big Birds (24,000).

BIRD AGE (weeks)	SECONDS ON (5-minute timer)	NUMBER OF 36" FANS
1	30	2
2	60	2
3	60	3
4	90	3
5	120	3
6	120	4
7	150	4
8	180	4

price will be significant: $30 as opposed to $1,500, and the ammonia meter may not last more than a year or two in a poultry house.

Second, be sure to check the drinker line height and pressure. Adding additional water to the house through improper drinker operation will skew the tables and cost you money. It takes about 12,000 cubic feet of air to get rid of a gallon of water. So wasting five gallons of water, will increase your ventilation rates by 1,000 cubic feet per minute. If the fresh air also has to be heated, you will probably use an additional half-gallon of propane per hour.

Phosphorus runoff from fields and ammonia entering the air are two problems associated with poultry litter. The amount of water soluble phosphorus in litter varies depending on its source and management. For example,

- fresh broiler litter contains 1.23 grams of water soluble phosphorus per kilogram of litter,
- stacked litter, 2.29 grams;
- dead bird compost, 2.15 grams;
- caged layer manure, 2.68 grams; and
- turkey litter, 3.02 grams.

The addition of alum (aluminum sulfate) has been reported to reduce ammonia levels in the house and to decrease phosphorus runoff when the litter is spread on pasture. The reduction in phosphorus runoff have been as high as 87 percent.

Other litter additives are available in addition to alum that, by acidifying the litter, are reported to decrease the levels of ammonia in the air of poultry houses. Alum is the only one that is reported to also reduce phosphorus runoff when the treated litter is applied to the land. The acidification of the litter is also reported to reduce the levels of bacteria in the litter thus having a potential food safety benefit.

Concerns have been expressed over the safety of workers applying alum to the litter. As a result, the manufacturer now supplies it in a low-dust granular form and suggests the use of goggles and particle dust masks by the individual applying the alum to the litter.

References

Czarick, M. and M.P. Lacy. 1997. Ammonia Levels Need to Be Monitored for Ventilation Effects. Poultry Times, June 16, pp. 22-23.

Moore, P.A. Jr. 1995. Phosphorus Precipitation in Poultry Litter with Al, Ca and Fe Amendments. Completed Research, Project 102. Southeasten Poultry and Egg Association, Tucker, Georgia.

Moore, P.A., Jr., P.C. Daniel, D.R. Edwards, and D.M. Miller. 1996. Evaluation of Chemical Amendments to Reduce Ammonia Volatilization from Poultry Litter. Poultry Science 75:315-320.

Moore, P.A., Jr., W.E. Huff, T.C. Sauer, T.C. Daniel, and D.R. Edwards. 1996. A Simple Method for Measuring Ammonia Volatilization from Poultry Litter. Presentation at the 85th Annual Meeting of the Poultry Science Association, Inc., July 8-12, in Louisville, KY.

Paul, J.W., P.K. Barton, D. Kermode, and T.A. Scott. 1997. Measuring Ammonia Emissions from Poultry Broilers Fed Balanced Amino Acid Diets. Agriculture and Agri-Food Canada, Pacific Agricultural Research Center, Agassiz, BC, Canada.

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300
5720 Uptain Road
Chattanooga, TN 37411
Tel: 423 855-6470
Fax: 423 855-6607

An Overview of Poultry Mortality Management

Responsibility for the safe and nonwasteful management of dead birds — a challenge for the poultry industry — is a practical problem that growers face on a near daily basis. It begins with choosing the best method for the proper disposal of the carcasses. Because dead birds constitute a large portion of the total wastes generated in poultry production, their disposal must be biologically secure, environmentally safe and cost effective.

Most normal mortalities occur during the first and last two weeks of the growing cycle for broilers and from 10 to 13 weeks of age for layers. Normal mortality for broiler production is 3 to 5 percent over the production cycle or about 0.1 percent per day. Thus, for example, in a flock of 100,000 broilers grown 49 days, as many as 5,000 may die. A single grower, assuming that a typical broiler house holds 20,000 birds weighing 2 to 4 pounds, may have as many as 85 pounds of dead birds to dispose of each day near the end of the growing cycle. A roaster operation may have to dispose of as many as 115 pounds per day, and a turkey operation may dispose of 150 to 200 pounds per day.

Mortality rates in other kinds of poultry operations will be similar to or somewhat lower than the rate for broilers. The exact number of daily mortalities will vary depending on the number of birds on hand as well as their size and age. Massive die-offs, catastrophic losses, and spent (unproductive) hens are additional challenges.

Burial in specifically designed pits, incineration, and rendering are the most common methods of disposal, though environmental, economic, and practical concerns have fueled interest in composting as a fourth alternative. Each of these methods is supported by best management practice guidelines. Newer technologies, for example, small-bin composting, fermentation, and refrigeration, are also emerging in field trials as individuals, the industry, and agricultural researchers seek to meet the challenge of mortality management.

Burial Pits

Burial pits are not always practical and may not always be permitted. The earliest burial pits (which were only adequate for very small operations) were simply holes dug in the ground with a small opening at the top. Depending on geologic and weather conditions, such pits will almost certainly affect water quality. Therefore, for many poultry producers, they are no longer an option given the intensity and concentration of today's industry. Where burial pits are still allowed, they generally require a permit and must be properly "constructed," sized, and located. They must also be tightly covered for safety and to prevent odors.

Incineration

Incineration is an acceptable and popular alternative to the use of burial pits. It is also biologically safe (the burning destroys pathogens), and poses no threat to surface or groundwater though care must be taken to insure that smokestacks do not create air quality problems or nuisance odors.

Historically, incineration has been the most costly method of mortality disposal. However, a new generation of improved incinerators may defeat this obstacle, particularly since the newer equipment also complies with air quality standards.

The Composting Alternative

Composting dead birds emerged as an acceptable method of mortality disposal only in the 1980s. Composting, however, is an ancient and natural waste-management technique that continued to be practiced with little change throughout the 18th and 19th centuries. In all that time, composting methods and speed differed little from the decomposition of organic matter that occurs naturally. The current use of composting as a managed method of mortality disposal improves on that technique to fulfill the biological, environmental, and cost criteria that must be met to qualify as an approved method. Pathogens cannot survive the increased temperatures associated with composting, odor and insects can be controlled, and air and water quality are protected. As an additional advantage, composting results in an inoffensive and value added end product that can be stockpiled until needed as a fertilizer or soil amendment. Each carcass is, in fact, 2 to 9 percent nitrogen, 1 to 4 percent total phosphorus, and 1 to 7 percent total potassium.

Rendering

Rendering may be the safest way to dispose of mortalities, at least from an environmental point of view. It, like composting, adds value to the end product — in this case, the carcasses are processed into biologically safe, protein and nutrient-enriched feed-mill products, such as feather meal and other dietary supplements for poultry and other animals.

Major drawbacks to rendering are the difficulty of transporting the carcasses to the renderer's plant while they are still fresh, and concern that disease or disease-causing organisms might be picked up in the vehicle or at the rendering plant and unintentionally returned to the farm.

On-farm fermentation offers growers a way to preserve the carcasses until they can be delivered to the renderer. The carcasses are collected, put through a grinder and mixed with a carbohydrate. Bacteria common in the birds' intestines ferment the carbohydrate to lactic acid, which neutralizes pathogens but preserves the nutrients, thus permitting the product to be held a longer time on the farm. Refrigeration or freezing is another method to preserve dead birds prior to their delivery to a rendering plant.

Decision Criteria

Growers must carefully consider the trade-offs — the differences in resource requirements and outcomes involved in these mortality management practices — and the effect of local conditions and personal preferences to determine the method of mortality management that best fulfills their need. Table 1 compares the methods by cost and in relation to size, environmental concern, and marketing considerations. Other characteristics may be important to some growers.

In all cases, unsanctioned methods, such as feeding the carcasses to hogs or other domestic animals or abandoning them in sinkholes or creeks or in the wild, should not be attempted. Nor can dead birds be delivered to municipal landfills. Dead bird disposal is a potential health hazard and a regulated activity. Growers must choose the permitted disposal method that best suits their management style and perform it according to strictly maintained standards to ensure sanitary conditions and the least possible environmental consequences.

Growers should check with their state agencies (environmental, agricultural, and animal veterinary medicine) to be certain that their plans comply with all dead animal disposal regulations. The USDA Natural Resources Conservation Service and Cooperative Extension Service offices can be of assistance.

More detailed discussions of burial pits, incineration, rendering, and composting as methods for managing dead birds can be found in subsequent fact sheets in this section of the handbook.

References

Blake, J.P. 1993. Mortality Management. Presentation. Poultry Waste Management and Water Quality Workshop. Southeastern Poultry and Egg Association, Atlanta, GA.

Crews, J.R., J.O. Donald, and J.P. Blake. 1995. An Economic Evaluation of Dead Bird Disposal Systems. Circular ANR-914. Alabama Cooperative Extension Service, Auburn, AL.

Payne, V.W.E., and J.O. Donald. 1991. Poultry Waste Management and Environmental Protection Manual. Circular ANR-580. Alabama Cooperative Extension Service, Auburn, AL.

Table 1.—Characteristics of Dead-Bird Disposal Systems.

	EXISTING TECHNOLOGIES				EMERGING TECHNOLOGIES	
Item	Disposal Pit	Incineration	Large-Bin Compost	Small-Bin Compost	Fermentation	Refrigeration
Initial investment cost	M	L	M	L	H	H
Variable cost	L	H	M	M	M	H
Fixed cost	M	L	M	L	M	H
Value of by-product	N	N	H	H	M	M
Net cost	L	H	M	L	M	H
Cost sensitivity to size	L	L	H	L	H	L
Flock size limitations	L	M	L	H	L	L
Environmental concern	H	M	L	L	N	N
Market constraints	N	L	N	L	H	H

KEY: H=high M=medium L=low N=none

Adapted from Crews, Donald, and Blake, 1995.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PMM / 1 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Burial — A Disposal Method for Dead Birds

The burial of dead birds in trenches, open pits, and landfills is rarely an acceptable method of dead bird disposal. In Arkansas and Alabama, no new in-ground burial pits are permitted — and states that do permit them consider this option the least desirable method or the method of last resort for mortality management. Until recently, however, burial was the only practical method some growers had to dispose of their dead birds — despite its potential for water pollution. Its use is now hedged with various guidelines and restrictions, such as construction requirements, loading rates, and setback distances from water resources, residences, and property lines. In all cases, the pits must be fabricated.

Pit Design and Fabrication

A fabricated burial pit is an open-bottomed, reinforced hole in the ground that has one or more openings at the top through which carcasses are dropped. An airtight cover above the openings prevents odors from escaping. The pit provides an environment in which aerobic and anaerobic microorganisms can consume most of the organic material. Only the feathers and bones should be left. Although disposal pits require minimal labor and supervision, they must be maintained in a sanitary, legal, and socially acceptable manner.

Fabricated pits should be made of concrete block, poured concrete, or treated timbers. Some prefabricated pits can be purchased from septic tank dealers and delivered to the farm ready for installation. Under no circumstances, however, should the pit be simply a hole in the ground dug with a backhoe and lined with tin. The decomposition process will produce very little water inside the pit, but the pit should be covered with soil and planted to vegetation to carry water away from the pit and to protect it from access by heavy equipment.

The openings — also called drop chutes — are made of plastic (PVC) pipes, which protrude out of the mound at intervals of five feet. The chutes should have tightly fitted but removable covers. The bottom of the pit is earthen with holes at intervals up the sides.

Location

Location guidelines established by state agencies to protect water resources should be carefully observed. Generally, a disposal pit should be located at least 200 to 300 feet from dwellings and the nearest water well, 50 feet from property lines, 25 feet from the poultry house and 100 to 300 feet from any flowing stream or public body of water.

Before constructing a disposal pit, make certain that the soil composition is acceptable. Bedrock (especially limestone) and sandy soils should be avoided. Locate pits in soil where good surface runoff will occur. Sandy soils are not suitable for pit installations.

To prevent groundwater contamination, the pit's lowest point should be at least five feet above the highest known water table and at least five feet above bedrock to keep contamination from traveling along a rock fissure. To prevent water from seeping into the pit, construction on a slope, floodplain, or low-lying area should be avoided and in some states is not permitted.

Pit Size

The pit itself should be at least six feet deep with reinforced walls. Its size will depend on several factors, including the expected mortal-



Properly constructed disposal pits are made of concrete block, poured concrete, or treated timbers.

ity rate of the flock, bird size, and environmental conditions. Use the following table to estimate pit size:

TYPE OF MORTALITY	PIT SIZE IN CUBIC FEET PER 1,000 BIRDS
Broilers	50
Turkeys (to 18 weeks)	100
Layers (commercial)	55

For broiler mortalities, for example, if you have a 5 percent mortality rate in a flock of 20,000 and you raise five flocks per year, your burial pit should contain at least 250 cubic feet of disposal space. That is, it should be about six feet deep, six feet wide, and about seven feet long. Sometimes it can be more convenient to use several smaller pits to prevent overloading. In cooler climates, the pit size should be larger to accommodate a slower rate of decomposition. Keep in mind that some states may have maximum loading rates depending on the area's vulnerability to groundwater pollution.

Durability and Cost

The life of the pit will depend on its location and whether it is properly sized, constructed, and managed. To ensure total decomposition, the pit must be operated efficiently to protect the bacterial population. High acidity, for example, will retard the decomposition of dead birds. Disposal pits are most efficient during warmer months when bacterial action is greatest. Decomposition is slowed by winter temperatures or by accumulation of water in the pit. Grinding the carcasses or splitting open the dead birds (puncturing the abdominal cavity) will expel gases, increase the pit's efficiency, and extend its life.

The cost of constructing disposal pits varies widely depending on the materials used, site conditions, and the size of the pit. Geologic conditions — rocky soil, for example — can make digging expensive. As pit size increases, heavier construction is required for walls and tops; thus, higher costs are incurred. For a well-built pit, a useful life of five years is not uncommon, and some producers have reported that pits can be useful for eight to 10 years. Replacement is required when the pit is full.

Operation

After a pit is constructed, producers should check their facilities twice daily for mortalities and transfer them immediately to the pit. (Current law requires dead animals to be properly disposed of within 24 hours.) Covers on the drop chutes should be kept closed at all times to prevent odor and restrict access by children, animals, and rodents. Certain insects in a disposal pit are beneficial to the decomposition of the carcasses, but insects should not be allowed to develop into a nuisance. With proper handling the disposal pit costs nothing to maintain except for the labor of collecting the carcasses.

Drawbacks

Burial pits may attract flies and scavengers, and they may emit offensive odors. Further, today's farm may have insufficient land space for burial pits, or the capacity of the pits may be limited in winter. If the oxygen supply is insufficient, the decomposition process will be arrested. Slacked lime can be added to the burial pit to break down the tissue of the dead birds. It

will also, in effect, sterilize the remains. If the site has poor soils or a high water table, groundwater pollution is a distinct possibility.

Before constructing or installing a prefabricated disposal pit, poultry producers should consult with their state's veterinary specialist, other agricultural offices, and environmental or natural resource agencies. These agencies may regulate the use of burial pits or disallow their use entirely, so seeking expert guidance before production begins often saves time and money. Local USDA Natural Resources Conservation Service or Cooperative Extension Service offices can provide technical assistance to growers who want to use disposal pits as part of their mortality management plans.

References

Arkansas Soil and Water Conservation Commission and the Water Resources Center. No date. Water Quality and Poultry Disposal Pits. Fact Sheet 2. Arkansas Soil and Water Conservation Commission, Little Rock AR.

Donald, J.O., and J.P. Blake. 1990. Use and Construction of Poultry Burial Pits. DTP Circular 10/90-013. Alabama Cooperative Extension Service, Auburn University, Auburn, AL.

Wineland, M.J., and T.A. Carter. 1987. Poultry Science and Technology Guide — Proper Disposal of Dead Poultry. PS&T Guide No. 19. North Carolina Agricultural Extension Service, Raleigh.

Other pages in this handbook contain more detailed information on these subjects. Permission is hereby granted to producers, growers, and associations serving the poultry industry to reproduce this material for further distribution. The Poultry Water Quality Consortium is a cooperative effort of industry and government to identify and adopt prudent uses of poultry by-products that will preserve the quality of water for everyone.

PMM / 2 — 9/98

POULTRY WATER QUALITY CONSORTIUM
6100 Building, Suite 4300 • 5720 Uptain Road • Chattanooga, TN 37411
Tel: 423 855-6470 • Fax: 423 855-6607

Incineration — A Disposal Method for Dead Birds

Incineration, or cremation, is a safe method of carcass disposal and may be the method of choice in areas plagued by poor drainage and rocky soils. The major advantage of incineration is its ability to curtail disease. It is biologically secure, and it does not create water pollution problems. Even its by-product — ashes — is minimal, easy to dispose of, and unlikely to attract rodents or pests.

On the other hand, incinerators can be a costly item to install and operate and are expected to become more expensive as fuel costs rise. Further, while incineration destroys pathogens and poses no risk to water, its effect on air quality must be carefully monitored by poultry growers who choose this method of mortality management.

Incineration is not, then, a casual or inexpensive undertaking. Barrels or other homemade vessels are unsatisfactory burners and have serious consequences for the grower if they result in air pollution or unpleasant odors. Using incineration to manage poultry mortalities must be carefully planned: it must comply with dead animal regulations, meet all air quality standards, and justify investments in commercial equipment and the risk of increasing energy costs.

Notwithstanding these drawbacks, incineration is biologically the safest method of mortality management and simultaneously the method most likely to protect water resources. Producers considering this method of mortality management should consult with their state's agricultural, environmental, and veterinary medical agencies on the best way to incorporate this method. Agricultural incinerators do not generally require a permit, but they are designed to handle Type 4 wastes (e.g., animal remains, carcasses, organs, and solid tissue from farms and animal labs), but not other wastes (e.g., plastics and other organics).

Good Incinerator Design

A variety of commercial incinerators are available, and each one should be installed according to the manufacturer's specifications and local codes — typically outside, but under a roofed structure and away from any combustibles.

Incinerators should be sturdily built and able to accommodate daily mortalities. Indeed they should be sized to handle large loads and high temperatures; however, very large-scale loads, for example, loads running over 100 pounds per hour may require an operating permit. Growers should carefully estimate the capacity needed to manage daily mortalities and include other disposal methods in their resource management plans to cover situations in which heavy, unexpected losses can occur.

A variety of commercial incinerators are available.